

# **Geomajas user guide for developers**

**Geomajas Developers and Geosparc**

---

# **Geomajas user guide for developers**

by Geomajas Developers and Geosparc

v1.7.1

Copyright © 2010 Geosparc nv

---

---

---

# Table of Contents

I. Introduction .....	1
1. Preface .....	3
About this document .....	3
About this project .....	3
License information .....	3
Author information .....	4
II. Architecture .....	5
2. Architecture .....	7
Command .....	12
Pipelines .....	13
Pipeline architecture .....	13
Application in the back-end .....	14
Layer .....	14
Security .....	14
Security architecture .....	14
How is this applied ? .....	17
Server configuration .....	19
3. Plug-ins .....	20
4. Project structure .....	21
Face and plug-in registration .....	21
Module Overview .....	21
III. API .....	25
5. API contract .....	27
API annotation .....	27
Back-end API .....	27
Command and plug-in API .....	28
GWT face API .....	28
API compatibility and Geomajas versions .....	28
6. Commands .....	30
CommandDispatcher service .....	30
Provided commands .....	30
7. Layers .....	39
RasterLayerService .....	39
VectorLayerService .....	39
8. Security .....	40
Authentication versus authorization .....	40
What can be authorized .....	40
SecurityManager service .....	41
SecurityContext service .....	42
9. Pipelines .....	43
PipelineService .....	43
Configuration .....	43
Default pipelines .....	45
RasterLayerService .....	45
VectorLayerService .....	45
10. Utility Services .....	47
ConfigurationService .....	47
GeoService .....	47
DtoConverterService .....	47
FilterService .....	48
TextService .....	48

IV. Configuration .....	49
11. Configuration basics .....	51
web.xml .....	51
General principles .....	52
Geomajas configuration .....	53
12. Map configuration .....	54
Raster layer configuration .....	54
Raster layer info .....	54
Vector layer configuration .....	55
Vector layer info .....	55
Bean layer configuration .....	60
Client configuration .....	61
Map configuration .....	61
Client layer configuration .....	65
13. Security configuration .....	66
14. Transaction configuration .....	68
15. Coordinate Reference Systems .....	69
V. How-to .....	70
16. Writing your own commands .....	72
17. Create a plug-in .....	75
Using the plug-in archetype .....	75
Plug-in structure .....	75
Plug-in declaration and dependencies .....	75
18. Create a layer plug-in .....	76
Writing your own layer .....	76
19. Create a security plug-in .....	77
Writing your own security service .....	77
VI. Appendices .....	78
A. Migrating between Geomajas versions .....	80
Migrating between Geomajas 1.6.0 and Geomajas (back-end core) 1.7.1 .....	80
Migrating from Geomajas 1.5.4 to Geomajas 1.6.0 .....	80
Migrating from Geomajas 1.5.3 to Geomajas 1.5.4 .....	81
Migrating from Geomajas 1.5.2 to Geomajas 1.5.3 .....	82
General API changes .....	83
Configuration changes .....	83
Migrating from Geomajas 1.5.1 to Geomajas 1.5.2 .....	86
Migrating from Geomajas 1.5.0 to Geomajas 1.5.1 .....	86
Migrating from Geomajas 1.4.x to 1.5.0 .....	86

---

## List of Figures

2.1. Geomajas back-end and faces .....	7
2.2. Geomajas services .....	8
2.3. Geomajas for mashups .....	9
2.4. Geomajas dependencies .....	10
2.5. Geomajas back-end modules .....	11
2.6. Geomajas face and commands .....	12
2.7. Geomajas pipeline architecture .....	13
2.8. Security architecture .....	15
6.1. Geomajas face and commands .....	30
8.1. Security architecture .....	41
9.1. Geomajas pipeline architecture .....	43
12.1. Geomajas client configuration .....	61

---

## List of Tables

4.1. List of Geomajas application modules .....	22
4.2. List of Geomajas back-end modules .....	22
4.3. List of Geomajas build-tools modules .....	23
4.4. List of Geomajas documentation modules .....	23
4.5. List of Geomajas face modules .....	23
4.6. List of Geomajas plug-in modules .....	24
4.7. List of Geomajas test modules .....	24
6.1. CopyrightCommand .....	31
6.2. GetConfigurationCommand .....	31
6.3. GetMapConfigurationCommand .....	32
6.4. GetRasterTilesCommand .....	32
6.5. GetVectorTileCommand .....	33
6.6. LogCommand .....	34
6.7. MergePolygonCommand .....	34
6.8. PersistTransactionCommand .....	35
6.9. SearchAttributesCommand .....	35
6.10. SearchByLocationCommand .....	36
6.11. SearchFeatureCommand .....	37
6.12. SplitPolygonCommand .....	38
6.13. UserMaximumExtentCommand .....	38
12.1. Raster Layer info .....	55
12.2. VectorLayer info .....	56
12.3. Feature info configuration .....	57
12.4. BeanLayer configuration .....	60
16.1. Samples of command name resolution .....	73
A.1. Back end configuration changes .....	82
A.2. Client configuration changes .....	82
A.3. Back end configuration changes .....	84
A.4. Client configuration .....	85

---

## List of Examples

8.1. Allow full access to everybody .....	40
9.1. Simple pipeline definition .....	44
9.2. Layer specific pipeline which refers to a delegate .....	44
9.3. Extending a delegate pipeline .....	44
11.1. Defining spring configuration locations in web.xml .....	51
11.2. Dispatcher servlet declaration in web.xml .....	52
11.3. Spring configuration preamble .....	52
11.4. ClientApplicationInfo definition .....	53
12.1. Style info .....	56
12.2. Feature info .....	57
12.3. Style info .....	59
12.4. Attribute validator configuration .....	60
12.5. Client map configuration .....	62
12.6. Client map configuration .....	62
12.7. Client map configuration - scale configuration .....	63
12.8. Client map configuration .....	64
12.9. Tool configuration .....	64
12.10. Client map configuration .....	65
13.1. Allow full access to everybody .....	66
13.2. Partial staticsecurity configuration .....	67
15.1. Custom CRS addition .....	69
16.1. Example command template .....	72
16.2. Scan to assure command is available .....	73
16.3. Maven source plugin .....	74
16.4. staticsecurity source plugin - including source .....	74



---

# Part I. Introduction

---

---

# Table of Contents

1. Preface .....	3
About this document .....	3
About this project .....	3
License information .....	3
Author information .....	4

---

# Chapter 1. Preface

## About this document

Documentation for developer who want to use and extend the Geomajas GIS framework.

## About this project

Geomajas is a free and open source GIS application framework for building rich internet applications. It has sophisticated capabilities for displaying and managing geospatial information. The modular design makes it easily extendable. The stateless client-server architecture guarantees endless scalability. The focus of Geomajas is to provide a platform for server-side integration of geospatial data, allowing multiple users to control and manage the data from within their own browsers. In essence, Geomajas provides a set of powerful building blocks, from which the most complex GIS applications can easily be built. Key features include:

- Modular architecture
- Clearly defined API
- Integrated client-server architecture
- Built-in security
- Advanced geometry and attribute editing with validation
- Custom attribute definitions including object relations
- Advanced querying capabilities (searching, filters, style, ...)

See <http://www.geomajas.org/>.

## License information

Copyright © 2009-2010 Geosparc nv.

Licensed under the GNU Affero General Public License. You may obtain a copy of the License at <http://www.gnu.org/licenses/>

This program is distributed in the hope that it will be useful, but *without any warranty*; without even the implied warranty of *merchantability* or *fitness for a particular purpose*. See the GNU Affero General Public License for more details.

The project also depends on various other open source projects which have their respective licenses.

From the Geomajas source (possibly specific module), the dependencies can be displayed using the "mvn dependency:tree" command.

For the dependencies of the Geomajas back-end, we only allow dependencies which are freely distributable for commercial purposes (this for example excludes GPL and AGPL licensed dependencies).

# Author information

This framework and documentation was written by the Geomajas Developers. If you have questions, found a bug or have enhancements, please contact us through the user fora at <http://www.geomajas.org/>.

List of contributors for this manual:

- Pieter De Graef
- Jan De Moerloose
- Joachim Van der Auwera
- Frank Wynants

---

## **Part II. Architecture**

---

---

## Table of Contents


2. Architecture .....	7
Command .....	12
Pipelines .....	13
Pipeline architecture .....	13
Application in the back-end .....	14
Layer .....	14
Security .....	14
Security architecture .....	14
How is this applied ? .....	17
Server configuration .....	19
3. Plug-ins .....	20
4. Project structure .....	21
Face and plug-in registration .....	21
Module Overview .....	21

# Chapter 2. Architecture

Geomajas is an application framework which allows building powerful GIS application. We will try to look at the architecture starting from a high level overview, drilling down to discover more details.

At the highest level, Geomajas makes a distinction between the *back-end* and *faces*.

**Figure 2.1. Geomajas back-end and faces**



The back-end is where you configure your maps, layers and attributes/features. It is always server side. The back-end has an API for interaction with the outside world and for extension using plug-ins. While one of the main purposes of the back-end is to provide bitmaps and vector graphics for the maps and provide data about features to be rendered and edited, it contains no display code.

The actual display and editing is done in the faces. The back-end is agnostic of web (or other) display frameworks. Faces are often split in two modules, a sever-side module (which directly talks to the back-end using java calls) and serializes data to the client, and a client-side module which only talks to the server side module. The communication between the two modules is private to the face. The face itself provides a additional client API. This will typically provide details about available widgets, parameters for these widgets and other possible interactions (like message queues or topics you can subscribe to).


The purpose of Geomajas is to provide rich editing of GIS data in the browser, but the faces also make other applications possible. You could unlock the maps which are configured in Geomajas using a face which makes data available as web services (this would result in a face with only a server-side module). You could also build a java swing application using the Geomajas back-end by writing a swing face. This would result in a thick client application (possibly accessible using Java Web Start).

Geomajas contains two faces out-of-the-box.

The a dojo face, which uses the dojo toolkit JavaScript widget library in the browser, is mainly provided for backward compatibility. Up until Geomajas 1.4 this was the only face which existed. It integrates well with dojo but has the disadvantage that you need to develop in both java (for the server side) and JavaScript (for the client side) and that debugging can be a challenge.

Since 1.5 we also provide a GWT face. This allows all development to be done in Java and GWT will handle conversion to Javascript for code which needs to run in the browser. Obviously this integrates best with GWT based applications, but it can be combined with other web frameworks as well.

**Figure 2.2. Geomajas services**



The Geomajas back-end is built from many services which are wired together using dependency injection (DI). This wiring is partly done automatically, and partly through the configuration files. Thanks to the inversion of control (IoC) the back-end is very flexible and can be customized at will.


The client-server communication is done through the command dispatcher. This delegates to one of the action based services which handle the command. These typically interact with one or more of the topic based services (though the command could also handle everything directly). The most important built-in topic based services are the raster and vector layer service. They are used to access the GIS data which is stored as either raster or vector layer.

All the services are running in a secured zone and will typically interact with the security context to verify access rights (or policies).

The layers access the actual GIS data, either directly or using some kind of transformation service (for example a GeoServer or MapServer instance).




Figure 2.3. Geomajas for mashups




With this advanced configuration, many integration options exist. One example is displayed above, the inclusion of Geomajas in an existing application. On the client side, you just have to include the map widget in your web application. On the server side, there are many options, but you could for example assure that the transactions are shared between your existing application and Geomajas.

Figure 2.4. Geomajas dependencies



As is the case for most powerful frameworks, Geomajas stands on the shoulder of giants. We use some of the major open source libraries in our framework (and we integrate with a lot more).

**Figure 2.5. Geomajas back-end modules**

The Geomajas back-end is itself built from several modules which are tied together using the Spring framework (<http://springframework.org/>). The Geomajas-api module is a set of interfaces which shields implementation details between the different modules. The base plumbing and some generic features are provided by the Geomajas-impl module.

There are four possible ways to extend the back-end.


- *command*: commands are used as main interaction point between the face (client side) and the Geomajas back-end. The retrieval of maps and features, calculations, updates on the features and all other functionalities which are available client-side are done using commands.
- *layer*: this groups a set of access options for all details of the layers of a map. A layer can be either raster or vector based. A vector layer can be editable. The features describing the objects which are part of the vector layer are accessed through the "feature model" which converts generic feature objects into something Geomajas can use (this way, there is no need for the generic feature objects to implement a "feature" interface, allowing the use of pojos). A feature contains a geometry and can contain attributes, style and labels. Attributes can be complex, including one-to-many and many-to-one relations to other objects.
- *pipeline*: all Geomajas back-end services which deal with layers are implemented using pipelines. A pipeline is a list of steps (actions) executed in order. Each pipeline can be overwritten for a layer, or you can change the default which is used when not overwritten for a layer.

Configuring pipelines can be used to change the rendering method, add additional rendering steps (for example marking the editable area on a tile), to introduce caching,...

- *security*: these modules contain the pluggable security features. You can configure the security services which are used to verify the validity of an authentication token and return the authorization objects based on it. These authorization objects can read the security policies from your (secure) policy store.

## Command

Figure 2.6. Geomajas face and commands



The interaction of the client faces with the Geomajas back-end is handled using commands.


1. When a command needs to be invoked (probably as result of a user interaction), the client will build a **CommandRequest** object. This contains the name of the command to be used, the parameters for the command, and optionally the user authentication token and language of the user interface.
2. This object is transferred to the face server. For web applications, this will typically be done using an AJAX request.
3. The face server will use this **CommandRequest** to invoke the **CommandDispatcher** service, which can be obtained using the Spring context.
4. The **CommandDispatcher** will start by invoking the **SecurityManager** to check whether the execution of the requested command is allowed. If it is allowed, the actual **Command** is obtained using the Spring context. The **CommandResponse** object is created and the command is executed.
5. The **Command** will now do its job, writing the results in the **CommandResponse** object. When problems occur during execution of the command, it can either write this into the response object or throw an exception.

6. When the command has executed, if it threw an exception, the dispatcher will add this in the response object. It will then convert any exceptions in the response object into some messages which may be sensible to the user (put the message in the correct language in the result object, assuring the "cause" chain is also included). Some extra information is also added in the response object (like command execution time).
7. The `CommandResponse` is returned to the face server.
8. The face server serializes the `CommandResponse` back to the face client.

When the command had something to do with rendering, then the response object is likely to contain a `Tile`.

## Pipelines

**Figure 2.7. Geomajas pipeline architecture**



## Pipeline architecture

All the layer access services provided by the Geomajas back-end are implemented by invoking a pipeline. Using `PipelineService`, blocks of functionality become reusable and highly configurable with limited coupling between the *pipeline steps*.

Some of the services which are implemented as `PipelineService` include:

- `RasterLayerService`: methods for accessing a raster layer, especially getting tiles for a raster layer.

- `VectorLayerService`: methods for accessing a vector layer, for example for getting the features or obtaining vector tiles.

Pipelines can nest. One of the steps in the default "vectorLayer.saveOrUpdate" pipeline will loop over all features to be updated and invoke the "vectorLayer.saveOrUpdateOne" pipeline for each.

Pipelines are server side only, client access is typically made available by invoking a command.

Pipelines are typically invoked for a specific layer. In that case, the default pipeline can be replaced by a layer specific pipeline. This way, layer specific configurations (like optimizations or specific rendering) can be applied. When a layer does not overwrite a pipeline, the default is used. Pipelines are always selected on pipeline name. You can create the layer specific pipeline by setting the layer id for which it applied. When several pipelines have the same steps, you can define the pipeline once, and refer to it later by using a pipeline delegate instead of a list of steps.

A pipeline consists of a number of steps. A pipeline is configured using a `PipelineInfo` object which details the pipeline id and steps. When a pipeline is started (using the `PipelineService`) it executes the pipeline steps until the pipeline is finished (a status which can be set by one of the steps), or until no more steps are available in the pipeline. Each step gets two parameters.

- a context which contains a map of (typed) objects which can be used to pass data between the steps (including initial parameters for the pipeline).
- the result object which can be filled or transformed during the pipeline's execution.

Pipelines can be extended. When a pipeline is defined, it is possible to include hooks for extensions. These are special no-op steps. When a pipeline is defined, you can either define all the pipeline steps, or refer to a delegate pipeline combined with a map of extension steps. The pipeline will then be based on the delegate pipeline with the extensions steps added after the hooks with matching names.

## Application in the back-end

All the methods in both `RasterLayerService` and `VectorLayerService` are implemented using pipelines.

## Layer

The layer extensions allow determining how a layer is built, which data is part of the layer, update and creation of extra data on a layer.

A `Layer` has some metadata (id, coordinate system, label, bbox, stored in the `LayerInfo` object) and allows you get obtain the layer data.

## Security

The data which is accessed using Geomajas can be security sensitive.

## Security architecture


Geomajas is built to be entirely independent of the authentication mechanism and the way to store policies.

Based on the user who is logged into the system, the following restrictions can apply:

- access rights to a command
- access rights for a layer

- a filter which needs to be applied for a layer
- a region which limits the data which may be accessed for a layer
- access rights on the features
- access rights on the individual attributes of the features

**Figure 2.8. Security architecture**



To assure the authentication mechanism is pluggable, an *authentication token* is used. The authentication token is used to determine the *security context*. The security context contains the *policies* which apply and which can be queried.

A list of *security services* can be defined (using Spring bean `security.SecurityInfo`). This list can be overwritten in configuration. By default the list is empty, which prohibits all access to everyone. The back-end does however include a security service which can be used to allow all access to everyone.

The security service is responsible for converting the authentication token into a list of *authorization objects*. The security manager will loop all configured security services (using Spring bean `security.SecurityInfo`) to find all the authorization objects which apply for the token. By default the security manager will stop looping once one of the security services gave a result. You can change this behaviour to always combine the authorization objects from all security services.

## Note

The system explicitly allows authentication tokens to be generated by different authentication servers. In that case for each authentication server, at least one security service should be

configured in Geomajas. However, when using such a configuration, you *have to* verify that the authentication tokens which are generated by the different servers cannot be the same.

In many systems (including RBAC systems) an authorization object matches a roles for the authenticated user.

Note that, as the actual authentication mechanisms are handled by the security services, Geomajas does not know any passwords or credentials. Similarly the secure, tamper-proof storage of policies is not handled by Geomajas either.

Details about the current authentication token and access to the policies (using the authorization objects) is available using the `SecurityContext`. The security context is thread specific. When threads are reused between different users, the security context needs to be cleared at the end of a request (group). This is normally handled by the faces.

The following general authorization checks exist:

- `isToolAuthorized(String toolId)`: true when the tool can be used. The "toolId" matches the "id" parameter which is used in the configuration as specified using the `ToolInfo` class.
- `isCommandAuthorized(String commandName)`: true when the command is allowed to be called. The "commandName" parameter is the same as the command name which is passed to the `CommandDispatcher` service.

And for each layer:

- `isLayerVisible(String layerId)`: true when (part of) the layer is visible.
- `isLayerUpdateAuthorized(String layerId)`: true when (some of) the visible features may be editable.
- `isLayerCreateAuthorized(String layerId)`: true when there is an area in which features can be created.
- `isLayerDeleteAuthorized(String layerId)`: true when (some of) the visible features may be deleted.
- `getVisibleArea(String layerId)`: only the area inside the returned geometry is visible (uses layer coordinate space). All features which fall outside the layer's `MaxExtent` area are also considered not visible.
- `getUpdateAuthorizedArea(String layerId)`: only the area inside the returned geometry may contain updatable features (uses layer coordinate space). All features which fall outside the layer's `MaxExtent` area are also considered not updatable.
- `getCreateAuthorizedArea(String layerId)`: only the area inside the returned geometry can new features be created (uses layer coordinate space). All features which fall outside the layer's `MaxExtent` area are also considered not creatable.
- `getDeleteAuthorizedArea(String layerId)`: only the area inside the returned geometry may contain deletable features (uses layer coordinate space). All features which fall outside the layer's `MaxExtent` area are also considered not deletable.
- `getFeatureFilter(String layerId)`: get an additional filter which needs to be applied when querying the layer's features.
- `isFeatureVisible(String layerId, InternalFeature feature)`: check the visibility of a feature.



- `isFeatureUpdateAuthorized(String layerId, InternalFeature feature)`: check whether a feature is editable.
- `isFeatureUpdateAuthorized(String layerId, InternalFeature oldFeature, InternalFeature newFeature)`: check whether the update contained in the feature is allowed to be saved.
- `isFeatureCreateAuthorized(String layerId, InternalFeature feature)`: check whether a feature is allowed to be created.
- `isFeatureDeleteAuthorized(String layerId, InternalFeature feature)`: check whether deleting the specific feature is allowed.
- `isAttributeReadable(String layerId, InternalFeature feature, String attributeName)`: check the readability of an attribute. The result can be feature specific.
- `isAttributeWritable(String layerId, InternalFeature feature, String attributeName)`: check whether an attribute is editable. The result can be feature specific.

These authorizations are split in several groups. The security service is not required to provide an implementation of each authorization test (see API), the security context always ensures that all methods are available.

Checking authentication and fetching the authorization details can be time consuming (not to mention the hassle of logging in again). To solve this, the results of the security services can be cached. When a security service can authenticate a token, the reply can contain details about the allowed caching. Three parameters are allowed to be passed, the `validUntil` and `invalidAfter` timestamps and an `extendValid` duration.

The security manager first checks the cache to find (valid) authentication results. A cache entry is only valid until the "validUntil" timestamp. When an entry is valid, `validUntil` may be extended until "now" plus "extendValid" duration. However, "validUntil" is never extended past "invalidAfter". When no data can be found in the cache, the security services are queried.

### Note

There may be multiple authentications stored for a authentication token. When one of them becomes invalid, they are all considered invalid.

### Note

Entering credentials is never handled by Geomajas. When the authentication token cannot be verified, a security exception is thrown. It is up to the client application (the face probably) to assure that a new authentication token is created.

The authorization have two possible results. When reading or rendering, all unauthorized data should simply be filtered without warning or exception. When trying to invoke a command or to create, update or delete, any attempt which is not authorized should result in a security exception.

The security uses the approach that all access is forbidden unless is is allowed. Hence, you will always need to configure at least one security service to assure the system is usable.

## How is this applied ?

The security is applied throughout Geomajas. A list of places (which is not necessarily complete) and some additional ideas for application follow.

Back-end services:

- `CommandDispatcher` verifies the existence of a `SecurityContext` and creates one if needed.
- `CommandDispatcher` verifies whether the command is allowed to be used.

`VectorLayerService`:

- Check layer access.
- Handle the "filter" for the layer (if any).
- Filter on visible area as this can increase query speed.
- Post-process features filtering unreadable attributes, set update flags, remove features which are not allowed.

Commands:

- `configuration.Get` and `configuration.GetMap`: layers which are invisible should be removed, tools which are not authorized should be removed, "editable" and "deletable" statuses on layers, features, attributes need to be set.
- `configuration.UserMaximumExtent`: max extent should only consider visible features.
- `feature.PersistTransaction`: making changes to attributes which are not editable should cause a security exception.
- `feature.SearchByLocation`: only return visible features and readable attributes.
- `feature.SearchFeature`: only return visible features and readable attributes.
- `geometry.Get`: only return the geometry for visible features.
- `geometry.MergePolygon`: no security implications.
- `geometry.SplitPolygon`: no security implications.
- `render.GetRasterTiles`: should only return data for visible layers, ideally post-processing the image to ensure only visible area is included (making the rest transparent).
- `render.GetVectorTile`: should only return data for visible layers, only display visible features, only return visible features, only render visible features. When attributes need to be included, only readable attributes should be included and the "editable" flag needs to be set.

Rendering:

- The individual rendering steps (especially the layer/feature model) can use the `SecurityContext` to filter the data they produce.
- Images can have areas masked which are not allowed to be seen.
- The rendering pipeline can include steps which check the security. This can make life easier on the layer model which are not guaranteed (or forced) to handle all security aspects. These are active by default but can be removed for speed (when you are sure this is double work).

Cache:

- The caching needs to consider the access rights when storing and retrieving data.

Face:

- The face is responsible for assuring a authentication token is included in all access to the back-end.
- The "get configuration" commands filter the data to assure invisible layer and attributes and tools which are not allowed are not displayed. No action needed.
- Specific tests on editability of individual features and attributes would be useful to assure the user does try to enter or modify data which cannot be saved.
- The face should ask for credentials again when the token was not available or is no longer valid. Specifically when a `GeomajasSecurityException` is received which code `ExceptionCode.CREDENTIALS_MISSING_OR_INVALID`.

## Server configuration

While this is not really touched by description above, the following system configuration issues are likely to be important when you want to secure your Geomajas application.

- Make sure the communication between the client and server uses encryption, possibly by using https. This prevents snooping of your data and/or hijacking the security token.
- Even if your application is using http for some reason, at the very least your authentication method should use https to prevent your passwords from being transmitted on the wire in cleartext. I would expect all authentication servers do this.
- Depending on your needs, it may make sense to store the data encrypted on the server. If you want that, you need a layer model which can access your secured data (possibly passing on the security token).

---

# Chapter 3. Plug-ins

Geomajas provides a basic set of functionality as part of the back-end core. This can be extended and made available using plug-ins. One of the functions of the back-end core is to act as a plug-in container. Plug-ins are optional libraries that extend the core functionality by taking advantage of the public API. There are three special types of plug-ins, faces, layers and security plug-ins. which provide extra features, faces, layers and other plu

Faces provide external interfaces for Geomajas. These give access to users or external systems to the configured data. The faces which are included in the Geomajas project are

- GWT face : our recommended face for displaying and editing GIS data in the browser. This allows you to build your web user interface in Java.
- dojo face : a face which allows web display and editing using dojo toolkit. The user interface needs to be developed using JavaScript.

The layer plug-ins provide access to the actual data which needs to be displayed as part of a maps. There are basically two types of layers, providing either raster data (bitmaps) or vector data. The layers which are provided as part of the normal distribution include

- *geomajas-layer-hibernate* (vector): allow access to any kind of features which are stored in a spatial (relational) database. The data is accessed using the hibernate and hibernate-spatial open source libraries.
- *geomajas-layer-geotools* (vector): access data from any vector data source which has a GeoTools data store defined for it (<http://geotools.org/javadocs/org/geotools/data/DataStore.html>).
- *geomajas-layer-google* (raster): include Google rasters. This allows access to the normal and satellite views provided by Google. You still have to make sure you comply with Google terms of use (<http://code.google.com/apis/maps/>).
- *geomajas-layer-openstreetmap* (raster): support for raster data coming from the OpenStreetMap project (<http://www.openstreetmap.org/>).
- *geomajas-layer-wms* (raster): access data from a WMS server (<http://www.opengeospatial.org/standards/wms>).
- *geomajas-layer-shapeinmem* (vector): access data from an ESRI shape file which handled in memory. The actual data access if done using GeoTools (<http://www.esri.com/library/whitepapers/pdfs/shapefile.pdf>).

Other plug-ins allow extensions in functionality, either by providing additional commands or extending the rendering pipelines, or they provide additional security services.

- *geomajas-command*: set of commands which are provided as part of the standard distribution. This is so fundamental to using Geomajas that it is provided as a back-end module.
- *geomajas-plugin-printing*: printing extensions for the framework
- *geomajas-plugin-staticsecurity*: a basic security service which can be configured as part of the Spring configuration and does not use an external source for users or policies, making the security configuration entirely static.

The back-end also contains a set of spatial services. These include services for accessing raster and vector services and a set of utility services.

---

# Chapter 4. Project structure

The project is built from a large set of modules. A specific application can choose which modules are used or not. In principle, the back-end module are always required and at least one face and at least one layer plug-in. More plug-ins or faces can be added as needed.

## Face and plug-in registration

Plug-ins (which include faces) are automatically discovered when available on the classpath. This is done using two files: META-INF/geomajasContext.xml and META-INF/geomajasWebContext.xml.

The geomajasContext.xml file contains information about the plug-in, the dependencies for the plug-in (which are checked when the application context is built, assuring that the set of plug-ins is complete and can be combined) and contains copyright and license information for the plug-in and its dependencies. Additional beans and services can also be defined.

The geomajasWebContext.xml file is provided to allow additional endpoints to be added in the web tier. Geomajas normally installs a `DispatcherServlet` in the web.xml file to allow additional web endpoints to be added using Spring MVC.

## Module Overview

Different modules have different impacts and different purposes. Therefore different categories of modules are required. Geomajas has defined the following set of module categories (matching the directories in the source):

- *application*: working examples of applications using the Geomajas GIS framework.
- *backend*: these are essential Geomajas modules. Each Geomajas application needs these modules. However, you also need some a face and some plug-ins (like layers) or you won't be able to do much.
- *build-tools*: some modules which are useful for starting or building Geomajas or a Geomajas project.
- *documentation*: documentation modules, specifically the different Geomajas guides. These are the general guides, each of the plug-ins also has a documentation module.
- *face*: faces that present a certain Geomajas client interface to the user.
- *plugin*: modules that extend Geomajas. This can either add new functionality, add support for a certain type of data source, provide a security service or a combination.
- *test*: modules which are used for (integration) testing of Geomajas.

Full list of Geomajas modules:

**Table 4.1. List of Geomajas application modules**

Name	Purpose
geomajas-dojo-example	Example application using the dojo face. Is more advanced than the dojo-simple demo. Can be useful as template project when starting a new dojo based Geomajas application which uses project specific JavaScript code.
geomajas-dojo-simple	Simple example project using the dojo face. Can be a useful template project when starting a new dojo based Geomajas application.
geomajas-gwt-example	Example application using the GWT face which serves both as showcase and test application.
geomajas-gwt-simple	Simple example project using the GWT face. Very similar to the GWT archetype which can be used to start a new GWT based Geomajas project.

**Table 4.2. List of Geomajas back-end modules**

Name	Purpose
geomajas-api	Stable interfaces. Reference guide for other modules.
geomajas-api-experimental	Experimental interfaces. This contains some experimental stuff which may be promoted to the supported API when useful, or may be changed or dumped. As this is <i>not</i> part of the API, it may change between revisions.
geomajas-command	Lists all basic commands.
geomajas-common-servlet	Code which is shared by the different faces which are servlet based.
geomajas-impl	Main library with default implementations.
geomajas-testdata	Module which contains data which is used for testing Geomajas.

**Table 4.3. List of Geomajas build-tools modules**

Name	Purpose
geomajas-checkstyle	Module which contains the checkstyle definitions which should be adhered to for all code in the Geomajas source tree.
geomajas-dep	This module can be included in your "dependencyManagement" section to set default versions for many possible dependencies. This includes the current release versions of all Geomajas project modules and their major dependencies. The versions can always be overwritten in your pom. It does not indicate that module versions play well together (though they should if the API contract is adhered). This module should never contain snapshot builds.
geomajas-maven-dojo	Maven plugin which helps to combine all the JavaScript code for dojo, Geomajas and the project itself. This is usually referred to as the "shrink" or "shrinksafe" step.
geomajas-maven-plugin	Maven plugin which is used for generating the documentation. It extracts excerpts from the code to allow inclusion in the docbook guides.
geomajas-parent	parent project which includes some Geomajas specific settings like copyright, java version, checkstyle etc.
geomajas-plugin-archetype	Archetype for starting a new plugin.

**Table 4.4. List of Geomajas documentation modules**

Name	Purpose
contributorguide	Guide for contributors to the project. Includes information about compilation of the project, coding style, how to contribute to the documentation, JIRA guidelines etc.
devuserguide	Guide for developers who want to use Geomajas in their applications.
enduserguide	Guide for end-users who use the Geomajas widgets. This guide should probably be included in the application documentation.
style	Style module for conversion of the docbook files to usable output.
xslt	Transformation module for conversion of the docbook files to usable output.

**Table 4.5. List of Geomajas face modules**

Name	Purpose
geomajas-face-dojo	Modules for the dojo face, including documentation.
geomajas-face-gwt	Modules for the GWT face, including the documentation.

**Table 4.6. List of Geomajas plug-in modules**

Name	Purpose
geomajas-layer-geotools	Support for any data format GeoTools supports.
geomajas-layer-google	Support for GoogleMaps raster format.
geomajas-layer-hibernate	Support for database formats through Hibernate.
geomajas-layer-openstreetmap	Support for OpenStreetMap raster format.
geomajas-layer-wms	Support for the WMS raster format.
geomajas-plugin-printing	Adds printing capabilities beyond printing in the browser, by delivering the map as PDF.
geomajas-plugin-staticsecurity	Simple security service which allows including the entire security configuration in the Spring configuration files, making the configuration static.
geomajas-plugin-caching	Caching plug-in which allows improved speed by calculating data only once.

**Table 4.7. List of Geomajas test modules**

Name	Purpose
geomajas-test-integration	Integrations tests, currently mostly testing the security handling.



---

## Part III. API

---

---

## Table of Contents

5. API contract .....	27
API annotation .....	27
Back-end API .....	27
Command and plug-in API .....	28
GWT face API .....	28
API compatibility and Geomajas versions .....	28
6. Commands .....	30
CommandDispatcher service .....	30
Provided commands .....	30
7. Layers .....	39
RasterLayerService .....	39
VectorLayerService .....	39
8. Security .....	40
Authentication versus authorization .....	40
What can be authorized .....	40
SecurityManager service .....	41
SecurityContext service .....	42
9. Pipelines .....	43
PipelineService .....	43
Configuration .....	43
Default pipelines .....	45
RasterLayerService .....	45
VectorLayerService .....	45
10. Utility Services .....	47
ConfigurationService .....	47
GeoService .....	47
DtoConverterService .....	47
FilterService .....	48
TextService .....	48

---

# Chapter 5. API contract

## API annotation

As Geomajas is a framework for building enterprise application, it is important to be very accurate about what exactly is considered part of the API, specifically which classes and interfaces and which methods in these classes and interfaces are considered as part of the API.

For this reason, we have introduced the "@Api" annotation. A class or interface is only considered part of the public API when it is annotated using "@Api". When all public methods in the class or interface are considered part of the API, you could use "@Api(allMethods = true)". The alternative is to annotate the individual methods.

The API includes many interfaces. These interfaces should only be implemented by client code when they are annotated by "@UserImplemented". All other interfaces are provided to indicate the methods available on instances which are obtained through the API or Spring wiring and may have extra methods added in future versions.

All classes and methods which are indicated with "@Api" should also have a "@since" javadoc comment indicating the version in which the class or method was added to the API.

### Note

Please beware that only the annotations determine whether something is part of the API or not. The manual may discuss things which are not considered API, probably because they are experimental.

## Back-end API

The full details about the API can be found in the published javadoc, available on the Geomajas site at <http://www.geomajas.org/gis-documentation>. There you can find the links for the different versions.

The API for the Geomajas back-end is contained in the geomajas-api module. This contains only interfaces, exceptions and data transfer objects. The data transfer objects are classes which only contain getters and setters. The back-end API is divided in the following packages:

- *command*: interfaces, services and data transfer objects related with the command extension points.
- *configuration*: data transfer objects which are used for defining the configuration in Geomajas.
- *geometry*: Geomajas geometry related data transfer objects.
- *global*: some general interfaces, annotations and exceptions which are relevant for a combination of several extension points or the entire API.
- *layer*: interfaces, services, exceptions, data transfer objects and some internal objects related with the layers and objects in a layer. These include the definition of a layer, tiles, features and feature models.
- *security*: interfaces, services and data transfer objects related with the security extension points and security handling.
- *service*: utility services provided by Geomajas.

The back-end also contains a module `geomajas-api-experimental`. This contains some experimental stuff which may be promoted to the supported API when useful, or may be changed or dumped. As this is *not* part of the API, it may change between revisions.

## Command and plug-in API

For commands and plug-ins, the same rule applies as for the back-end API. That means that the `@Api` annotation indicates the stability of the interfaces, classes and methods.

These classes can typically be found in packages containing `command.dto` for command request and response objects or packages containing `configuration` for objects which are expected to be defined from the Spring configuration files.

The command name is also considered part of the API when the implementing class is annotated using the `@Api` annotation.

## GWT face API

The GWT plug-in also uses the `@Api` annotation to indicate classes and methods which are supported to remain stable between minor versions of the face.

You can expect to find this annotation on all widgets, though it is likely that not all public methods will be considered part of the API.

## API compatibility and Geomajas versions

Versions have the structure `"major.minor.revision"`. Geomajas uses an even-odd versioning scheme for the "minor" part.

The major number indicates major changes in the framework and thus gives no guarantee about API compatibility with previous major versions.

Versions with an even minor part are considered stable and suitable for production use. Odd minor versions are used for development to work on and test new features to be released in the next stable version. The API for Geomajas needs to be upward compatible for all stable versions with same major number. Specifically this means that

- No API classes or interfaces may be removed.
- No API classes or interfaces may be renamed.
- No API classes or interfaces may have their package name modified.
- No API methods may be removed.
- No API methods may have their signature changed.
- No methods may be added to classes annotated using `@UserImplemented`.

Additionally, all methods and classes which are added should include an indication of the version in which the class and/or method was added. This is done using the `@since` javadoc comment for the methods, class or interface.


Because of the guarantees about API, the use of the "`@Deprecated`" annotation only indicates that a method or class is not recommended to be used. The method or class will not be removed in future versions with the same major number.

# Chapter 6. Commands

## CommandDispatcher service

The command dispatcher is the main command execution service. It accepts commands serializable data for executing a command and returns a response which can again be serialized. It is the main entry point into the back-end for use by the faces.

Figure 6.1. Geomajas face and commands



The following methods are provided:

- `CommandResponse execute(String commandName, CommandRequest commandRequest, String userToken, String locale)`: given the command name, request object, user token and locale, try to execute the requested command. The result, including any exception which may have been thrown are included in the returned response object.

## Provided commands

The commands are all registered in the Spring context. The "registry key" as indicated below is used to retrieve the commands. These are services, so a singleton should be sufficient for this.

The default naming for the keys is derived from the fully qualified class name. This is automatically assigned when the command is in a (sub package of) the "command" package. To determine the

bean name, all parent packages of the "command" package are removed. Then the name is simplified. It will end up having "command." as prefix, optionally followed by a package, followed by the name. As there already is a "command" prefix, the "Command" suffix is removed from the name if present. When the resulting name starts or end with the sub package, then that is removed as well. For example the "org.geomajas.command.configuration.GetConfigurationCommand" class will get "command.configuration.Get" as registry key.

**Table 6.1. CopyrightCommand**

<b>CopyrightCommand</b>	
Registry key	command.general.Copyright
Module which provides this command	geomajas-command
Request object class	org.geomajas.command.EmptyCommandRequest
Parameters	none
Description	This allows you to obtain copyright and license information for Geomajas, it's dependencies, the plg-ins and the dependencies of the plug-ins. This can be used to display that information in a "about" box to assure the copyright and license conditions are adhered.
Response object class	org.geomajas.command.dto.CopyrightResponse
Response values	List of CopyrightInfo objects for the dependencies. Any duplicates are removed based on the copyright info key.

**Table 6.2. GetConfigurationCommand**

<b>GetConfigurationCommand</b>	
Registry key	command.configuration.Get
Module which provides this command	geomajas-command
Request object class	org.geomajas.command.EmptyCommandRequest
Parameters	none
Description	Get the client side configuration information. This returns information about all maps which have been configured.
Response object class	org.geomajas.command.dto.GetConfigurationResponse
Response values	<ul style="list-style-type: none"> <li>• <i>name</i>: name of the application.</li> <li>• <i>maps</i>: list of configured maps for the application. Note that the layer information which is contained in the maps has the coordinates transformed according to the crs of the map.</li> <li>• <i>screenDpi</i>: screen resolution in dots per inch.</li> </ul>

**Table 6.3. GetMapConfigurationCommand**

<b>GetMapConfigurationCommand</b>	
Registry key	command.configuration.GetMap
Module which provides this command	geomajas-command
Request object class	org.geomajas.command.dto.GetMapConfigurationRequest
Parameters	<ul style="list-style-type: none"> <li>• <i>mapId</i>: id of map for which the information should be returned.</li> </ul>
Description	Get the client side configuration information for the specified map.
Response object class	org.geomajas.command.dto.GetMapConfigurationResponse
Response values	<ul style="list-style-type: none"> <li>• <i>mapInfo</i>: information about the requested map. Note that the layer information which is contained in the maps has the coordinates transformed according to the crs of the map.</li> </ul>

**Table 6.4. GetRasterTilesCommand**

<b>GetRasterTilesCommand</b>	
Registry key	command.render.GetRasterTiles
Module which provides this command	geomajas-command
Request object class	org.geomajas.command.dto.GetRasterTilesRequest
Parameters	<ul style="list-style-type: none"> <li>• <i>crs</i>: coordinate reference system that the map uses.</li> <li>• <i>bbox</i>: total bounding box wherein to fetch raster tiles.</li> <li>• <i>scale</i>: current scale in the client side map.</li> <li>• <i>layerId</i>: the id of the raster layer to fetch tiles for.</li> </ul>
Description	Retrieve a set of raster tiles as image links for a given layer within a certain bounding box expressed in a certain coordinate reference system.
Response object class	org.geomajas.command.dto.GetRasterTilesResponse
Response values	<ul style="list-style-type: none"> <li>• <i>rasterData</i>: list of RasterTile objects.</li> <li>• <i>nodeId</i>: identifier to be used in the DOM tree.</li> </ul>



**Table 6.5. GetVectorTileCommand**

<b>GetVectorTileCommand</b>	
Registry key	command.render.GetVectorTile
Module which provides this command	geomajas-command
Request object class	org.geomajas.command.dto.GetVectorTileRequest
Parameters	<ul style="list-style-type: none"> <li>• <i>layerId</i>: the id of the vector layer to fetch a tile in.</li> <li>• <i>code</i>: the unique code of the tile to retrieve.</li> <li>• <i>scale</i>: the current scale on the map, client side.</li> <li>• <i>panOrigin</i>: translation for the tile on the client-side.</li> <li>• <i>filter</i>: extra filter that can be used to filter out data.</li> <li>• <i>crs</i>: the map's coordinate reference system.</li> <li>• <i>renderer</i>: should the server render to SVG or VML?</li> <li>• <i>styleInfo</i>: extra styles that can override the originally configured styles.</li> <li>• <i>paintGeometries</i>: should the geometries be painted in the tile? This is true by default.</li> <li>• <i>paintLabels</i>: should labels be painted in the tile?</li> <li>• <i>featureIncludes</i>: indication of which data to include in the feature. Possible values (add to combine): 1=attributes, 2=geometry, 4=style, 8=label. Default value is to include everything.</li> </ul>
Description	Fetches a single tile for a vector layer. The tile can contain both vectors and labels. This command is used to paint vector layers in the map.
Response object class	org.geomajas.command.dto.GetVectorTileResponse
Response values	<ul style="list-style-type: none"> <li>• <i>tile</i>: the actual resulting tile.</li> </ul>

**Table 6.6. LogCommand**

<b>LogCommand</b>	
Registry key	command.general.Log
Module which provides this command	geomajas-command
Request object class	org.geomajas.command.dto.LogRequest
Parameters	<ul style="list-style-type: none"> <li>• <i>level</i>: log level, 0 for debug, 1 for info, 2 for warn, 3 for error.</li> <li>• <i>statement</i>: string which needs to be logged.</li> </ul>
Description	This allows you to send a statement to the server side which will be logged there.
Response object class	org.geomajas.command.CommandResponse
Response values	none

**Table 6.7. MergePolygonCommand**

<b>MergePolygonCommand</b>	
Registry key	command.geometry.MergePolygon
Module which provides this command	geomajas-command
Request object class	org.geomajas.command.dto.MergePolygonRequest
Parameters	<ul style="list-style-type: none"> <li>• <i>polygons</i>: array of polygons that need to be merged</li> <li>• <i>allowMultiPolygon</i>: is a MultiPolygon allowed when merging multiple polygons?</li> </ul>
Description	This command allows the user to merge multiple polygons into a single polygon or multipolygon.
Response object class	org.geomajas.command.dto.MergePolygonResponse
Response values	<ul style="list-style-type: none"> <li>• <i>geometry</i>: the resulting geometry after the merge.</li> </ul>

**Table 6.8. PersistTransactionCommand**

<b>PersistFeatureTransactionCommand</b>	
Registry key	command.feature.PersistTransaction
Module which provides this command	geomajas-command
Request object class	org.geomajas.command.dto.PersistTransactionRequest
Parameters	<ul style="list-style-type: none"> <li>• <i>featureTransaction</i>: the actual transaction object. Contains a list of features as they where, and a list of features as they should be.</li> <li>• <i>crs</i>: the map's coordinate reference system.</li> </ul>
Description	Persist a single transaction on the backend (create, update, delete of features).
Response object class	org.geomajas.command.dto.PersistTransactionResponse
Response values	<ul style="list-style-type: none"> <li>• <i>featureTransaction</i>: the same transaction that was sent to the server. Unless something went wrong, in which case this could be null.</li> </ul>

**Table 6.9. SearchAttributesCommand**

<b>SearchAttributesCommand</b>	
Registry key	command.feature.SearchAttributes
Module which provides this command	geomajas-command
Request object class	org.geomajas.command.dto.SearchAttributesRequest
Parameters	<ul style="list-style-type: none"> <li>• <i>layerId</i>: the layer to search in.</li> <li>• <i>attributeName</i>: the name of the attribute as configured in the feature info.</li> <li>• <i>filter</i>: a filter, to limit the list of returned features.</li> </ul>
Description	Search for attribute possible values for a certain attribute. This command is only used for many-to-one and one-to-many relationships, to search for possible values.
Response object class	org.geomajas.command.dto.SearchAttributesResponse
Response values	<ul style="list-style-type: none"> <li>• <i>attributes</i>: list of attribute values.</li> </ul>

**Table 6.10. SearchByLocationCommand**

<b>SearchByLocationCommand</b>	
Registry key	command.feature.SearchByLocation
Module which provides this command	geomajas-command
Request object class	org.geomajas.command.dto.SearchByLocationRequest
Parameters	<ul style="list-style-type: none"> <li>• <i>location</i>: geometry which should be used for the searching.</li> <li>• <i>queryType</i>: specify exactly whether to search, possible values are QUERY_INTERSECTS, QUERY_TOUCHES, QUERY_WITHIN or QUERY_CONTAINS.</li> <li>• <i>ratio</i>: if queryType is QUERY_INTERSECTS, you can additionally specify what percentage of overlap is enough to be included in the search.</li> <li>• <i>layerIds</i>: array of layer ids to search in.</li> <li>• <i>searchType</i>: determines whether to stop searching once something is found in one of the layers (in order of course), or whether to continue searching, and include matching features from all layers.</li> <li>• <i>crs</i>: the map's coordinate reference system. The <i>location</i> geometry will also be expressed in this crs.</li> <li>• <i>buffer</i>: before any calculation is made, it is possible to have the location geometry expanded by a buffer of this width (in crs space).</li> <li>• <i>featureIncludes</i>: indication of which data to include in the feature. Possible values (add to combine): 1=attributes, 2=geometry, 4=style, 8=label. Default value is to include everything.</li> </ul>
Description	This command allows you to search for features, based on geographic location.
Response object class	org.geomajas.command.dto.SearchByLocationResponse
Response values	<ul style="list-style-type: none"> <li>• <i>featureMap</i>: map with layer ids as key and a list of features as value. Only layers in which features were found are included in the map.</li> </ul>

**Table 6.11. SearchFeatureCommand**

<b>SearchFeaturesCommand</b>	
Registry key	command.feature.Search
Module which provides this command	geomajas-command
Request object class	org.geomajas.command.dto.SearchFeatureRequest
Parameters	<ul style="list-style-type: none"> <li>• <i>layerId</i>: id of layer in which features need to be searched.</li> <li>• <i>max</i>: maximum number of features to allow in the result. 0 means unlimited.</li> <li>• <i>crs</i>: crs which needs to be used for the geometry in the retrieved features.</li> <li>• <i>criteria</i>: array of criteria which need to be matched when searching. Each criterion contains the attribute name, the operator (options include "like" and "contains") and the value to compare. Note that the value usually needs to be contained in single quotes.</li> <li>• <i>booleanOperator</i>: operator which should be used to combine the different criteria when more than one was specified. Should be either "AND" or "OR". Default value is "AND".</li> <li>• <i>filter</i>: an additional layer filter which needs to be applied when searching.</li> <li>• <i>featureIncludes</i>: indication of which data to include in the feature. Possible values (add to combine): 1=attributes, 2=geometry, 4=style, 8=label. Default value is to include everything.</li> </ul>
Description	This command allows you to search for features, based criteria which allow matching on feature attributes. You can specify multiple search criteria and a filter.
Response object class	org.geomajas.command.dto.SearchFeatureResponse
Response values	<ul style="list-style-type: none"> <li>• <i>layerId</i>: id of the layer which contains the features. Equals the layerId parameter from the request.</li> <li>• <i>features</i>: array of features which match the search criteria. Any geometry contained in the features uses the request crs.</li> </ul>

**Table 6.12. SplitPolygonCommand**

<b>SplitPolygonCommand</b>	
Registry key	command.geometry.SplitPolygon
Module which provides this command	geomajas-command
Request object class	org.geomajas.command.dto.SplitPolygonRequest
Parameters	<ul style="list-style-type: none"> <li>• <i>geometry</i>: the geometry that needs splitting.</li> <li>• <i>splitter</i>: the splitting geometry (usually a LineString).</li> </ul>
Description	Split up a geometry into many pieces by means of a splitting geometry.
Response object class	org.geomajas.command.dto.SplitPolygonResponse
Response values	<ul style="list-style-type: none"> <li>• <i>geometries</i>: the list of resulting geometries after the split.</li> </ul>

**Table 6.13. UserMaximumExtentCommand**

<b>UserMaximumExtentCommand</b>	
Registry key	command.configuration.UserMaximumExtent
Module which provides this command	geomajas-command
Request object class	org.geomajas.command.dto.UserMaximumExtentRequest
Parameters	<ul style="list-style-type: none"> <li>• <i>layerIds</i>: list of layers to include.</li> <li>• <i>includeRasterLayers</i>: true when raster layers should be included. Defaults to false.</li> <li>• <i>crs</i> : crs which should be used for the response.</li> </ul>
Description	Get the bounding box of the visible features across the requested layers (visible area for the raster layers).
Response object class	org.geomajas.command.dto.UserMaximumExtentResponse
Response values	<ul style="list-style-type: none"> <li>• <i>bounds</i> : bounding box.</li> </ul>

---

# Chapter 7. Layers

Layers allow access to data which needs to be displayed in a map.

For the existing layers, the details about configuring you map to include that layer are included in the map configuration chapter.

## RasterLayerService

All access to raster layers should be done using the raster layer service. The following methods exist

- `List<RasterTile> getTiles(String layerId, CoordinateReferenceSystem crs, Envelope bounds, double scale)` throws `GeomajasException`: this method allows you to obtain the list of raster tiles which need to be displayed for the given bounds at the requested scale.

## VectorLayerService

Vector layers and the data contained within are accessible using the vector layer service. You should not try to access the layers directly. This service assures that the security constraints are adhered. Following access methods are available

- `void saveOrUpdate(String layerId, CoordinateReferenceSystem crs, List<InternalFeature> oldFeatures, List<InternalFeature> newFeatures)` throws `GeomajasException`: allows creating or updating several features. You have to pass both the old features (null or the feature before it was modified) and the new value of the feature. The two are compared to determine whether to create, update or delete.
- `List<InternalFeature> getFeatures(String layerId, CoordinateReferenceSystem crs, Filter filter, NamedStyleInfo style, int featureIncludes)` throws `GeomajasException`: read all features from the layer which match the filter. You can specify which aspects of the feature need to be set.
- `List<InternalFeature> getFeatures(String layerId, CoordinateReferenceSystem crs, Filter filter, NamedStyleInfo style, int featureIncludes, int offset, int maxResultSize)` throws `GeomajasException`: read a batch of features from the layer which match the filter. You can specify which aspects of the feature need to be set..
- `Envelope getBounds(String layerId, CoordinateReferenceSystem crs, Filter filter)` throws `GeomajasException`: get the bounds of the visible features which match the filter. This can be useful for fit-to-page like functionality.
- `List<Attribute<?>> getAttributes(String layerId, String attributeName, Filter filter)` throws `GeomajasException`: get the list of possible attribute values.
- `InternalTile getTile(TileMetadata tileMetadata)` throws `GeomajasException`: get a vector tile.

---

# Chapter 8. Security

Geomajas has security built-in. If you don't provide a security configuration, nothing will be authorized. For unsecured access, you can add

## Example 8.1. Allow full access to everybody

```
<bean name="security.securityInfo" class="org.geomajas.security.SecurityInfo">
  <property name="loopAllServices" value="false"/>
  <property name="securityServices">
    <list>
      <bean class="org.geomajas.security.allowall.AllowAllSecurityService"/>
    </list>
  </property>
</bean>
```

which will allow all access to everybody, including full access to features which are only partly within configured bounds.

It is also possible to configure other security services, to allow authentication and authorization to be done by the services which are configured.

## Note

When configuring security services, it is important to assure that login is possible. Anything which is not explicitly allowed in *not* allowed, which likely includes the command which is used to login. You have to make sure that everybody can access the login command.

Specific configuration depends on the configured security services, details of which can be found in the specific plugin's documentation.

# Authentication versus authorization

The security infrastructure makes a clear distinction between authentication and authorization.

Authentication is the act of identifying the user and user the user is how he/she says he is (whether that person is "authentic"). In Geomajas the authentication will result in a authentication token which encapsulated that a user has provided valid credentials. The token in itself does not contain either information about the user or information about what is allowed or authorized (no policies). These can however be accessed using the token.

The Geomajas back-end core does not do authentication, though it is likely that your security plug-in either provide commands to allow creation of a token (by supplying user credentials) and invalidating the token (logout), or the plug-in will stipulate where this can be done (possibly supplying a redirect to an SSO service or similar).

Authorization on the other hand reads the policies which are in effect to determine what an authenticated user if allowed or disallowed to do and/or access. Geomajas only uses policies which allow access, Everything which is not explicitly allowed is disallowed.

# What can be authorized

Based on the user who is logged into the system, the following restrictions can apply:




- access rights to a command
- access rights for a layer
- a filter which needs to be applied for a layer
- a region which limits the data which may be accessed for a layer
- access rights on the features
- access rights on the individual attributes of the features

You can extend this by providing additional authentication interfaces which are also implemented by the authentication object returned by your security service. Details can be found in Chapter 19, *Create a security plug-in*.

## SecurityManager service

The security manager manages the (thread-local) security context. It delegates to the available security services to build the authentication objects and get the user information which is then stored in the in the security context. The security services themselves will check with the authentication server or service whether the token is still valid, and will get the policies from a policy server or service to populate the authentication objects with the credentials.

**Figure 8.1. Security architecture**



The SecurityManager service has the following methods:

- `boolean createSecurityContext(String authenticationToken) :` create the security context for this thread, based on the authentication token.
- `void clearSecurityContext() :` clear the security context for this thread.

## SecurityContext service

The security context allows access to the currently valid user's policies and some limited information (user id, name and organization). In your code, you just have to inject the security context. The face is responsible for assuring the current thread has the correct security context based on the credentials used when accessing the back-end (it will use the SecurityManager service to do that).


The security context contains all methods from the UserInfo and Authorization interfaces, plus some methods to get the current token and get the list of authentication objects which have been combined.

---

# Chapter 9. Pipelines

Pipelines are building blocks which are used in Geomajas to make certain aspects highly extend- and customizable. For more details, see the architecture the section called “Pipelines”.

**Figure 9.1. Geomajas pipeline architecture**



## PipelineService

The pipeline service helps you to execute a pipeline. It allows you to fetch a named pipeline which applies for a specific layer (either the layer specific pipeline or the default pipeline). It also has methods to create an empty pipeline context and execute a pipeline.

## Configuration

A pipeline can be defined by specifying the pipeline name and the pipeline steps.

### Example 9.1. Simple pipeline definition

```
<bean class="org.geomajas.service.pipeline.PipelineInfo">
  <property name="pipelineName" value="pipelineTest"/>
  <property name="pipeline">
    <list>
      <bean class="org.geomajas.internal.service.pipeline.Step1">
        <property name="id" value="s1"/>
      </bean>
      <bean class="org.geomajas.internal.service.pipeline.Step2">
        <property name="id" value="s2"/>
      </bean>
      <bean class="org.geomajas.internal.service.pipeline.Step3">
        <property name="id" value="s3"/>
      </bean>
    </list>
  </property>
</bean>
```

A pipeline can be layer specific and can refer to a delegate (bean reference). The use of the delegate means that the pipeline definition (list of steps) is copied from the delegate.

### Example 9.2. Layer specific pipeline which refers to a delegate

```
<bean id="inter" class="org.geomajas.service.pipeline.PipelineInfo">
  <property name="pipelineName" value="pipelineTest"/>
  <property name="layerId" value="inter"/>
  <property name="delegatePipeline" ref="stop" />
</bean>
```

When referring to the pipeline definition using a delegate, the pipeline can also be extended by inserting additional steps at the extension hooks. You can pass a map of "extensions" which are named steps. When a extension hook of the name is found, that step will be included in the pipeline just after the hook definition.

### Example 9.3. Extending a delegate pipeline

```
<bean id="hooked2" class="org.geomajas.service.pipeline.PipelineInfo">
  <property name="pipelineName" value="hookedTest"/>
  <property name="layerId" value="delegate"/>
  <property name="delegatePipeline" ref="hooked" />
  <property name="extensions">
    <map>
      <entry key="PreStep2">
        <bean class="org.geomajas.internal.service.pipeline.Step2">
          <property name="id" value="ps2"/>
        </bean>
      </entry>
    </map>
  </property>
</bean>
```

## Default pipelines

The default pipelines are detailed here. All the steps mentioned here have a hook before and after the step to allow customization of the pipeline. These hooks have the name of the step as mentioned here, with either "pre" or "post" as prefix (note that these keys are case dependent).

### RasterLayerService

#### getTiles()

- "Get" : get the raster tile.

### VectorLayerService

#### saveOrUpdate()

- "EqualSize" : verify that the list of old and new features match.
- "SaveOrUpdate" : this handles the save or update for the individual features using the pipeline below.

#### saveOrUpdate each feature

- "Delete" : delete the feature if it has been removed.
- "CheckId" : check that the id for the old and new feature match.
- "TransformGeometry" : assure the geometry is transformed to layer coordinate space.
- "Create" : handle the creation of a new feature.
- "Update" : update the feature.
- "UpdateSave" : save it back to the data store.
- "UpdateFeature" : and assure the feature itself reflects the state from the database.

#### getFeatures()

- "LayerFilter" : calculate the correct filter based on security and layer extent.
- "GetFeaturesStyle" : get the styles which are relevant for the features.
- "GetFeatures" : fetch and fill the features.

#### getBounds()

- "LayerFilter" : calculate the correct filter based on security and layer extent.
- "GetBounds" : calculate the bounds for the features which comply with the filter.

#### getAttributes()

- "LayerFilter" : calculate the correct filter based on security and layer extent.

- "GetAttributes" : get the attributes for the filtered features.

## **getTile()**

- "TileFilter" : calculate the correct filter based on security and tile extent.
- "GetFeatures" : fetch and fill the features.
- "TileTransform" : transform the tile to the requested coordinate reference system.
- "GetStringContent" : render the features to the requested string content.

---

# Chapter 10. Utility Services

The Geomajas back-end core also contains a set of utility services.

## ConfigurationService

This service allows you to easily access some of the configuration information.

Provided methods are:

- `VectorLayer getVectorLayer(String id)` : get a vector layer based on the layer id.
- `RasterLayer getRasterLayer(String id)` : get a raster layer based on the layer id.
- `Layer<?> getLayer(String id)` : get a layer (can be either vector or raster), based on the layer id.
- `ClientMapInfo getMap(String mapId, String applicationId)` : get the map with given id for a specific application.

## GeoService

GeoServices provides a set of methods which ease the working with geometries and related objects.

- `CoordinateReferenceSystem getCrs(String crs)` throws `LayerException` : get the CRS object based on the CRS id.
- `int getSridFromCrs(String crs)` : attempts to extract the SRID (Spatial Reference Id) from the CRS.
- `int getSridFromCrs(CoordinateReferenceSystem crs)` : attempts to extract the SRID (Spatial Reference Id) from the CRS.
- `MathTransform findMathTransform(CoordinateReferenceSystem sourceCrs, CoordinateReferenceSystem targetCrs)` throws `GeomajasException` : get the transformation which converts between two coordinate systems.
- `Geometry transform(Geometry source, CoordinateReferenceSystem sourceCrs, CoordinateReferenceSystem targetCrs)` throws `GeomajasException` : transform a geometry from source to target CRS.
- `Coordinate calcDefaultLabelPosition(InternalFeature feature)` : determine a default position for positioning the label for a feature.
- `Geometry createCircle(Point center, double radius, int nrPoints)` : get a geometry which approximates a circle (if only a geometry could contain curves).

## DtoConverterService

This service allows conversion between objects which are used internally (which may contain JTS or Geotools objects) and data transfer objects which can be used for communication with the outside world (including the faces).

There are two methods which are provided, `toInternal()` and `toDto()` and these are overloaded for many different types of objects.

## FilterService

`FilterService` allows you to build filters which can be applied when requesting vector features.

## TextService

Utility functions for calculating text and font related parameters server-side. These parameters could in principle be calculated more accurately on the displaying device itself, but unfortunately there is no support for this in browser environments.

- `Rectangle2D getStringBounds(String text, FontStyleInfo fontStyle) :` get the bounds for the given string.



---

## **Part IV. Configuration**

---

---

## Table of Contents

11. Configuration basics .....	51
web.xml .....	51
General principles .....	52
Geomajas configuration .....	53
12. Map configuration .....	54
Raster layer configuration .....	54
Raster layer info .....	54
Vector layer configuration .....	55
Vector layer info .....	55
Bean layer configuration .....	60
Client configuration .....	61
Map configuration .....	61
Client layer configuration .....	65
13. Security configuration .....	66
14. Transaction configuration .....	68
15. Coordinate Reference Systems .....	69

---

# Chapter 11. Configuration basics

Geomajas leverages the Spring framework for configuration. The initial configuration needs to be done using `web.xml`. There you need to indicate the files which contain the configuration information.

## `web.xml`

In your `web.xml` file, you need to assure the configuration is made available to the application, and you can indicate which files are used to contain the configuration. Though it is possible to put all configuration information in one file, we recommend splitting your configuration in several files. At least one file per application, possibly split further per client layer configuration, and one file for server-side configuration of each of the layers.

The listener class initialises the application context as needed for Geomajas. It appends the context configuration locations which are specified in the `contextConfigLocation` context parameter to the list of internal configuration locations and uses these to build the application context. When no location is specified, the files is searched on the class path. You can also use location prefixes as defined by Spring. To allow use of configuration file on the web context, use an empty location (just a colon as prefix, eg `"/WEB-INF/config.xml"`). Note that whitespace is used as separator which means that the path itself should not contain spaces.

These are defined using an excepts like the following:

### Example 11.1. Defining spring configuration locations in `web.xml`

```
<context-param>
  <param-name>contextConfigLocation</param-name>
  <param-value>
    org/geomajas/dojo/simple/*.xml
  </param-value>
</context-param>

<listener>
  <listener-class>org.geomajas.servlet.GeomajasContextListener</listener-cl
</listener>
```

You also need to define at least the dispatcher servlet and possible an additional servlet for your faces. The dispatcher servlet can be defined as follows.

**Example 11.2. Dispatcher servlet declaration in web.xml**

```
<servlet>
  <servlet-name>dispatcher</servlet-name>
  <servlet-class>org.springframework.web.servlet.DispatcherServlet</servlet-clas
  <init-param>
    <param-name>contextConfigLocation</param-name>
    <param-value>classpath*:META-INF/geomajasWebContext.xml</param-value>
    <description>Spring Web-MVC specific (additional) context files.</descript
  </init-param>
  <load-on-startup>3</load-on-startup>
</servlet>

<servlet-mapping>
  <servlet-name>dispatcher</servlet-name>
  <url-pattern>/d/*</url-pattern>
</servlet-mapping>
```

## General principles

Each configuration file needs the following header:

**Example 11.3. Spring configuration preamble**

```
<beans xmlns="http://www.springframework.org/schema/beans"
  xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"
  xmlns:util="http://www.springframework.org/schema/util"
  xmlns:aop="http://www.springframework.org/schema/aop"
  xmlns:tx="http://www.springframework.org/schema/tx"
  xsi:schemaLocation="
http://www.springframework.org/schema/beans http://www.springframework.org/schema/
http://www.springframework.org/schema/util http://www.springframework.org/schema/u
http://www.springframework.org/schema/aop http://www.springframework.org/schema/ao
http://www.springframework.org/schema/tx http://www.springframework.org/schema/tx/
```

This defines the most common schemas which are needed. The configuration is built by populating the configuration classes. The configuration classes are split up between client-side and back-end. Only the back-end classes are necessary to configure the back-end, which behaves as a catalog of layers. The client side classes are used to define applications and maps, which are purely client-side concepts in the Geomajas architecture.

The back-end classes exist in the have a class name ending in "Info" and are mostly found in the `org.geomajas.configuration` package. These classes are actually used to represent the DTO part of the back-end layers, thereby allowing to transfer information or metadata of these layers to the client.

Configuration is done using the Spring Framework. We will give some notions here, but for a full introduction to Spring, please read the reference documentation <http://static.springsource.org/spring/docs/3.0.x/spring-framework-reference/>.

Each configuration file can contain one or more bean definitions, which correspond to actual Java bean instances. You can set all the properties of the objects using this configuration file. Primitive types can be set directly using a string representation of the value. When the value is another bean, then it can either be defined in-line, or you can use a reference. You can choose whether the referenced bean is defined

in the same file or a different one. As long as the bean name is unique, and the location is added in the `contextConfigLocation` context parameter in the `web.xml` file, the reference is resolved.

It is possible to define a bean with the same name (or id) more than once. In that case, the last occurrence will be used.

## Geomajas configuration

The initial bean which needs to be defined is a bean indicating the *client application info*.

### Example 11.4. ClientApplicationInfo definition

```
<bean name="gwt-simple" class="org.geomajas.configuration.client.ClientApplicationInfo">
  <property name="maps">
    <list>
      <ref bean="sampleFeaturesMap" />
      <ref bean="sampleOverviewMap" />
    </list>
  </property>
</bean>
```

As you can see, this defines the list of maps for the application. It may (optionally) also define some additional user info and a screen DPI parameter. The DPI refers to the resolution in pixels per inch of your monitor, for a PC its usually 96 (the default) or 72.

There needs to be at least one `ClientApplicationInfo` bean. The bean name is used when requesting the application info.

---

# Chapter 12. Map configuration

The central configuration which needs to be done is the map and the collection of layers which are part of that map.

## Raster layer configuration

Raster layers are image-based layers which, depending on the type, may be configured to retrieve their images from WMS, Google Maps or OpenStreetMap (tile) servers. All raster layer implementations implement the `org.geomajas.layer.RasterLayer` interface, which means they provide an accessor for a `RasterLayerInfo` metadata object. The info object configuration is normally defined in the Spring configuration as part of the entire layer configuration. Depending on the type of layer, extra properties are needed to provide a full configuration.

## Raster layer info

For all raster layers, you will need to define a raster layer info object to define the back-end configuration for the layer. The exact meaning for some of the fields depend on the actual layer, but most important features include:

**Table 12.1. Raster Layer info**

Name	Description
dataSourceName	The name of the data source as used by the layer.
crs	The coordinate reference system, expressed as "EPSG:<srid>". Caveat: make sure this is the same as the maps' crs as full raster image reprojection is not supported! If the crs is not the same, an attempt will be done to rescale and align the center coordinates, though.
maxExtent	The bounds of the layer, specified in layer coordinates. After transformation to map coordinates, this determines the locations and absolute size of the tiles.
zoomLevels	<p>A list of scale values corresponding to the zoom levels at which the raster data should be fetched.</p> <p>An image or tile scale is obtained by dividing the size of the tile in pixels by the size of the tile in map units. For example, if the tile is 256 x 256 pixels and this corresponds to an area of 100 m x 100 m, the scale can be calculated as <math>256/100 = 2,56</math> pixels per meter. The inverse value of the scale is more often used and is sometimes called <i>theresolution</i>. Images are usually optimized or prerendered for a specific (set of) resolution(s), so it is important to specify these here if they are known. On top of that, some servers provide specific tile caching for these predefined resolutions (for example WMS-T).</p> <p>A word of caution concerning zoom levels : setting the zoom levels here will only make sure that tiles will be fetched at predefined levels but does not impose any restrictions on the zoom levels of the map itself. If the zoom levels of the map have different values or are not specified at all (arbitrary zooming), raster images will be stretched on the client side to accomodate for these differences.</p>
tileWidth	Width in pixels of the requested images.
tileHeight	Height in pixels of the requested images.

The location of the images or tiles is defined by calculating the real width and height (based on the resolution) and "paving" the maximum extent with tiles starting at the origin (x,y) of the extent. If no resolutions are predefined, the tiles are calculated by dividing the maximum extent by successive powers of 2. Make sure the width/height ratio of the maximum extent corresponds to the width/height ratio of the tile.

## Vector layer configuration

Vector layers contain homogeneous vectorial features. All vector layer implementations implement the `org.geomajas.layer.VectorLayer` interface, which means they provide an accessor for a `VectorLayerInfo` metadata object. The info object configuration is normally defined in the Spring configuration as part of the entire layer configuration. Depending on the type of layer, extra properties are needed to provide a full configuration.

The definition of the actual layer is similar to the definition of a raster layer.

## Vector layer info

For the layer configuration, you have to create the layer info object.

### Example 12.1. Style info

```
<bean name="airportsInfo" class="org.geomajas.configuration.VectorLayerInfo">
  <property name="layerType" value="POINT" />
  <property name="crs" value="EPSG:4326" />
  <property name="maxExtent">
    <bean class="org.geomajas.geometry.Bbox">
      <property name="x" value="-87.4" />
      <property name="y" value="24.3" />
      <property name="width" value="8.8" />
      <property name="height" value="6.4" />
    </bean>
  </property>
  <property name="featureInfo" ref="airportsFeatureInfo" />
  <property name="namedStyleInfos">
    <list>
      <ref bean="airportsStyleInfo" />
    </list>
  </property>
</bean>
```

This defines the details common to both raster and vector layers, like layer id, crs, layer type, max extent (bounding box) etc.

The following table describes the properties of the `VectorLayerInfo` object:

**Table 12.2. VectorLayer info**

Property	Description
layerType	This property determines the type of the default geometry of the features. The following types are supported: POINT, LINESTRING, POLYGON, MULTIPOINT, MULTILINESTRING and MULTIPOLYGON
crs	The coordinate reference system, expressed as "EPSG:<srid>". This is probably determined by the layer, but has to be specified anyhow as we have no autodetection in place yet..
maxExtent	The bounds of the layer, specified in layer coordinates. After transformation to map coordinates, this determines the locations and absolute size of the tiles.
featureInfo	The feature metadata
namedStyleInfos	The list of predefined style metadata objects which define the named styles for this layer

The feature metadata can be found in the `FeatureInfo` object. This object contains the complete feature type description (id, attributes and geometry) as well as the validation rules for the attributes. An example definition of this object is given below:



**Example 12.2. Feature info**

```

<bean class="org.geomajas.configuration.FeatureInfo" name="airportsFeatureInfo">
  <property name="dataSourceName" value="airprtx020" />
  <property name="identifier">
    <bean class="org.geomajas.configuration.PrimitiveAttributeInfo">
      <property name="label" value="Id" />
      <property name="name" value="ID" />
      <property name="type" value="LONG" />
    </bean>
  </property>
  <property name="geometryType">
    <bean class="org.geomajas.configuration.GeometryAttributeInfo">
      <property name="name" value="the_geom" />
      <property name="editable" value="true" />
    </bean>
  </property>
  <property name="attributes">
    <list>
      <bean class="org.geomajas.configuration.PrimitiveAttributeInfo">
        <property name="label" value="Name" />
        <property name="name" value="NAME" />
        <property name="editable" value="true" />
        <property name="identifying" value="true" />
        <property name="type" value="STRING" />
      </bean>
      <bean class="org.geomajas.configuration.PrimitiveAttributeInfo">
        <property name="label" value="County" />
        <property name="name" value="COUNTY" />
        <property name="editable" value="true" />
        <property name="identifying" value="false" />
        <property name="type" value="STRING" />
      </bean>
    </list>
  </property>
</bean>

```

The following table describes the properties of the FeatureInfo object:

**Table 12.3. Feature info configuration**

Name	Description
dataSourceName	This name is used by the layer to internally reference the source that provides the data. Depending on the type of layer, this could be a table name (geotools-postgis), a shape file name (geotools-shapeinmem, in this case there is a 1-to-1 correspondence with the geotools datastore), a WFS layer name (geotools-wfs) or a java class name (hibernate).
identifier	Metadata of the primitive attribute that provides a unique identification of the feature.
geometryType	Metadata of the geometrical attribute that provides the default geometry of the feature.
attributes	Metadata of all other attributes

This defines the identifier, geometry object and attributes for the feature.

Attributes can be either primitive attributes or association attributes. Primitive attributes represent primitive Java types as well as some common types like Date and String. The following primitive attribute types are defined: `BOOLEAN`, `SHORT`, `INTEGER`, `LONG`, `FLOAT`, `DOUBLE`, `CURRENCY`, `STRING`, `DATE`, `URL` and `IMGURL`. Association attributes represent non-primitive Java types. There are two types of association attributes defined: `MANY_TO_ONE` and `ONE_TO_MANY`. These reflect the many-to-one and one-to-many relationships as defined in an entity-relationship model and can only be used in conjunction with the `HibernateLayer`.

Last but not least, you can define one or more named style definitions which should be used for rendering of the layer. The actual style that is being used by the client is determined in the client configuration, but you predefine a number of styles (of type `NamedStyleInfo`) here for later reference in the client configuration.

Each style object is itself composed of a number of feature styles (`FeatureStyleInfo`) and a label style (`LabelStyleInfo`). You can define formulas to determine which feature style should be used. The first style whose formula passes will be applied for the feature.

### Example 12.3. Style info

```
<bean class="org.geomajas.configuration.NamedStyleInfo" name="airportsStyleInfo">
  <property name="featureStyles">
    <list>
      <bean class="org.geomajas.configuration.FeatureStyleInfo">
        <property name="name" value="Airports (Florida)" />
        <property name="fillColor" value="#FF3333" />
        <property name="fillOpacity" value=".7" />
        <property name="strokeColor" value="#333333" />
        <property name="strokeOpacity" value="1" />
        <property name="strokeWidth" value="1" />
        <property name="symbol">
          <bean class="org.geomajas.configuration.SymbolInfo">
            <property name="rect">
              <bean class="org.geomajas.configuration.RectInfo">
                <property name="w" value="12" />
                <property name="h" value="12" />
              </bean>
            </property>
          </bean>
        </property>
      </bean>
    </list>
  </property>
  <property name="labelStyle">
    <bean class="org.geomajas.configuration.LabelStyleInfo">
      <property name="labelAttributeName" value="NAME" />
      <property name="fontStyle">
        <bean class="org.geomajas.configuration.FontStyleInfo">
          <property name="color" value="#FEFEFE" />
          <property name="opacity" value="1" />
        </bean>
      </property>
      <property name="backgroundStyle">
        <bean class="org.geomajas.configuration.FeatureStyleInfo">
          <property name="fillColor" value="#888888" />
          <property name="fillOpacity" value=".8" />
          <property name="strokeColor" value="#CC0000" />
          <property name="strokeOpacity" value=".7" />
          <property name="strokeWidth" value="1" />
        </bean>
      </property>
    </bean>
  </property>
</bean>
```

## Validation

Most feature attributes should be validated before they can be saved to a file or database. Validation is a concern that stretches across many layers of a typical application: there is usually a need for client-side validation (making the application more user friendly) , server-side validation (to protect the server from invalid data) as well as database validation (to preserve data integrity). Preferably validation rules should be defined as much as possible in a single place to avoid conflicts and duplication.

Our attribute configuration supports several types of validation by defining a "validator" property inside the attribute:

#### Example 12.4. Attribute validator configuration

```
<property name="validator">
  <bean class="org.geomajas.configuration.validation.ValidatorInfo">
    <property name="toolTip" value="Is this city a capital city or not? (Y or
    <property name="errorMessage" value="Invalid value: The value must be eith
    <property name="constraints">
      <list>
        <bean class="org.geomajas.configuration.validation.NotNullConstrai
        <bean class="org.geomajas.configuration.validation.PatternConstrai
          <property name="regex" value="[YN]$" />
        </bean>
      </list>
    </property>
  </bean>
</property>
```

This property contains some general validator information and a set of constraints that should be applied to the attribute. The available constraint types have been based on the new JavaBeans standard: JSR-303.

## Bean layer configuration

Bean layer provides an in-memory layer which is not persisted in any way. The features can be defined in the configuration file using some specialised beans. It is particularly useful for testing.

TODO.....

**Table 12.4. BeanLayer configuration**

Name	Description
features	List of features, which should be org.geomajas.layer.bean.FeatureBean instances.



### Example 12.5. Client map configuration

```
<bean name="sampleFeaturesMap" class="org.geomajas.configuration.client.ClientMapI
  <property name="crs" value="EPSG:4326" />
  <property name="displayUnitType" value="CRS" />
  <property name="initialBounds">
    <bean class="org.geomajas.geometry.Bbox">
      <property name="x" value="-180"/>
      <property name="y" value="-90"/>
      <property name="width" value="360"/>
      <property name="height" value="180"/>
    </bean>
  </property>
  <property name="layers">
    <list>
      <ref bean="wmsLayer" />
      <ref bean="countries110mLayer" />
    </list>
  </property>
```

The crs evidently refers to the map's coordinate reference system. The display unit type determines the unit type of the scale bar (METRIC, ENGLISH or CRS). The initial bounds determine the visible area of the map at startup time. The layers refers to the client layer info objects, not the server layer info or layer instances.

Additionally, a lot of style information can be included in the map configuration. This includes information like background colour, styles which should be used for selected points, lines and polygons and whether scale bare or pan buttons should be enabled.

### Example 12.6. Client map configuration

```
<property name="backgroundColor" value="#F0F0F0" />
<property name="lineSelectStyle">
  <bean class="org.geomajas.configuration.FeatureStyleInfo">
    <property name="fillOpacity" value="0" />
    <property name="strokeColor" value="#FF6600" />
    <property name="strokeOpacity" value="1" />
  </bean>
</property>
<property name="pointSelectStyle">
  <bean class="org.geomajas.configuration.FeatureStyleInfo">
    <property name="fillColor" value="#FFFF00" />
  </bean>
</property>
<property name="polygonSelectStyle">
  <bean class="org.geomajas.configuration.FeatureStyleInfo">
    <property name="fillColor" value="#FFFF00" />
    <property name="fillOpacity" value=".5" />
  </bean>
</property>
<property name="scaleBarEnabled" value="true" />
<property name="panButtonsEnabled" value="true" />
```

An other important aspect of the map is the scale configuration. The scale configuration allows to define a maximum scale beyond which the user is not allowed to zoom in. This is not needed for zooming out as

there is always a maximum bounds defined for the map (either explicitly or calculated as the union of the layer bounds). Next to that you can define a list of zoom levels. By default, the map will allow zooming to arbitrary scale levels but you may wish to enforce certain scale or zoom levels upon the user (like Google Maps does). By doing so, continuous zooming will no longer be possible and any zooming action will "snap" to the predefined scale levels.

### Example 12.7. Client map configuration - scale configuration

```
<property name="scaleConfiguration">
  <bean class="org.geomajas.configuration.client.ScaleConfigurationInfo">
    <property name="maximumScale" value="1:1000" />
    <property name="zoomLevels">
      <list>
        <value>1:128000000</value>
        <value>1:64000000</value>
        <value>1:32000000</value>
        <value>1:16000000</value>
        <value>1:8000000</value>
        <value>1:4000000</value>
        <value>1:2000000</value>
        <value>1:1000000</value>
        <value>1:500000</value>
        <value>1:100000</value>
        <value>1:25000</value>
        <value>1:15000</value>
        <value>1:10000</value>
        <value>1:5000</value>
        <value>1:2500</value>
        <value>1:1000</value>
      </list>
    </property>
  </bean>
</property>
```

Scales can be defined in 2 possible notations:

- the 1 : x notation (see the above listing) is most commonly used in geographics and expresses the ratio between 1 meter on the screen and 1 meter on the earth's sphere
- the floating point notation (e.g. 0.0001) is used by us to express the number of pixels on the screen that correspond to 1 unit on the map (1 pixel per 10000 map units in our example)

Both scale definitions serve a different purpose. The 1 : x scale should give you an idea of what the true scale is at which the map is shown, although in practice this may depend on the DPI (actually PPI) and pixel size of your device. The floating point scale (which has units of pixel/m or pixel/degree) is used to precisely define the resolution of raster images on the screen. If you use floating point notation, you can make sure that the scales that are being used in an application are the same as those of the raster layer(s) that lies beneath (see raster layer configuration). Otherwise the raster images may get blurry or unreadable when they need to be resized.

A map typically also contains a tool bar. If you want one, you have to specify the tools it should include.

### Example 12.8. Client map configuration

```
<property name="toolbar">
  <bean name="sampleFeaturesMapToolbar" class="org.geomajas.configuration.client
    <property name="tools">
      <list>
        <ref bean="ZoomIn" />
        <ref bean="ZoomOut" />
        <ref bean="ZoomToRectangleMode" />
        <ref bean="PanMode" />
        <ref bean="ToolbarSeparator" />
        <ref bean="ZoomPrevious" />
        <ref bean="ZoomNext" />
        <ref bean="ToolbarSeparator" />
        <ref bean="EditMode" />
        <ref bean="MeasureDistanceMode" />
        <ref bean="SelectionMode" />
      </list>
    </property>
  </bean>
</property>
```

Obviously the tools themselves need to be defined as well. You can pass some parameters to the tools. An example tool definition look like this.

### Example 12.9. Tool configuration

```
<bean name="ZoomIn" class="org.geomajas.configuration.client.ClientToolInfo">
  <property name="parameters">
    <list>
      <bean class="org.geomajas.configuration.Parameter">
        <property name="name" value="delta" />
        <property name="value" value="2" />
      </bean>
    </list>
  </property>
</bean>
```

Note that the tool id and the names of the parameters are interpreted by the client, so it is the client face which defines the possible values.

Last but not least, you can also configure the layer tree component which may be connected to the map.



### Example 12.10. Client map configuration

```
<property name="layerTree">
  <bean name="sampleFeaturesTree" class="org.geomajas.configuration.client.C
    <property name="tools">
      <list>
        <ref bean="LayerVisibleTool" />
        <ref bean="LayerLabeledTool" />
        <ref bean="ShowTableAction" />
        <ref bean="LayerRefreshAction" />
      </list>
    </property>
    <property name="treeNode">
      <bean class="org.geomajas.configuration.client.ClientLayerTreeNode
        <property name="label" value="Layers" />
        <property name="layers">
          <list>
            <ref bean="wmsLayer" />
            <ref bean="countries110mLayer" />
          </list>
        </property>
        <property name="expanded" value="true" />
      </bean>
    </property>
  </bean>
</property>
</bean>
```

This defines the tools which are available in the layer tree widget, and the tree of layers (as a node, which can contain a list of nodes etc).

Note that the layers are indicated by referring to the client configuration object.

## Client layer configuration

Layer configuration is split in two (linked) parts. You have to create the actual layer which is used in the back-end, and this layer needs to know the configuration information which is also used on the client side. Secondly, there is a distinction between raster and vector layers as they each needs a lot of specific information.

### Raster layer

TODO.....

### Vector layer

TODO.....

---

# Chapter 13. Security configuration

To make sure the system can be used, you have to configure the security to allow access. The easiest configuration is to allow access to everybody.

## Example 13.1. Allow full access to everybody

```
<bean name="security.securityInfo" class="org.geomajas.security.SecurityInfo">
  <property name="loopAllServices" value="false"/>
  <property name="securityServices">
    <list>
      <bean class="org.geomajas.security.allowall.AllowAllSecurityService"/>
    </list>
  </property>
</bean>
```

Any other configuration would depend on the available security services. For example, when using the staticsecurity plugin, the following could be defined.

**Example 13.2. Partial staticsecurity configuration**

```
<bean name="SecurityService" class="org.geomajas.plugin.staticsecurity.securit

<bean name="security.securityInfo" class="org.geomajas.security.SecurityInfo">
  <property name="loopAllServices" value="true"/>
  <property name="securityServices">
    <list>
      <ref bean="SecurityService"/>
      <bean class="org.geomajas.plugin.staticsecurity.security.LoginAllo
    </list>
  </property>
</bean>

<bean class="org.geomajas.plugin.staticsecurity.configuration.SecurityServiceI
  <property name="users">
    <list>

      <!-- User elvis has restricted attribute editing permissions on ro
      <bean class="org.geomajas.plugin.staticsecurity.configuration.User
        <property name="userId" value="elvis"/>
        <property name="password" value="BUOMyQ95onvc7gMrMjFtDQ"/> <!--
        <property name="userName" value="Elvis Presley"/>
        <property name="authorizations">
          <list>
            <bean class="org.geomajas.plugin.staticsecurity.config
              <property name="commandsInclude">
                <list>
                  <value>.*</value>
                </list>
              </property>
              <property name="visibleLayersInclude">
                <list>
                  <value>.*</value>
                </list>
              </property>
              <property name="updateAuthorizedLayersInclude">
                <list>
                  <value>beans</value>
                </list>
              </property>
```

Most notable in this example is the inclusion of two security services. The first is provided to allow login and logout (*only*) for everybody. The second defines users and authorizations (only the beginning of the configuration is displayed here).

---

# Chapter 14. Transaction configuration

Spring has support declarative transaction management, which relieves us from the burden of writing our own transaction demarcation and exception handling code. Of course, Spring transaction management has to be hooked up with the transaction definition and life cycle of the underlying data platform (hibernate, JTA, JDBC) . Each data access technology should provide its own implementation of the Spring class `PlatformTransactionManager`. You should check your plug-in documentation for details about configuring the transaction manager.

Transaction management is typically only needed for editable database layers (although we support and encourage it for read-only layers as well). There is currently no support for having multiple platform transaction managers, although configurations with multiple transaction managers should be possible. This will be investigated and fixed in the future. In practice this means that you currently must not mix editable layers which require a different transaction manager..

---

# Chapter 15. Coordinate Reference Systems

Geomajas uses GeoTools' gt-epsg-wkt module to define the coordinate reference systems which are available.

If you want to add extra coordinate reference systems, this can be done by defining them in the configuration. For example, Geomajas itself already defines the "EPSG:900913" crs (which one of the many codes for the Mercator projection used by Google Maps and OpenStreetMap).

## Example 15.1. Custom CRS addition

```
<bean class="org.geomajas.global.CrsInfo">
  <property name="key" value="EPSG:900913"/>
  <property name="crsWkt">
    <value>
PROJCS["Google Mercator",
  GEOGCS["WGS 84",
    DATUM["World Geodetic System 1984",
      SPHEROID["WGS 84", 6378137.0, 298.257223563, AUTHORITY["EPSG","7030"]],
      AUTHORITY["EPSG","6326"]],
    PRIMEM["Greenwich", 0.0, AUTHORITY["EPSG","8901"]],
    UNIT["degree", 0.017453292519943295],
    AXIS["Geodetic latitude", NORTH],
    AXIS["Geodetic longitude", EAST],
    AUTHORITY["EPSG","4326"]],
    PROJECTION["Mercator (1SP)", AUTHORITY["EPSG","9804"]],
    PARAMETER["semi_major", 6378137.0],
    PARAMETER["semi_minor", 6378137.0],
    PARAMETER["latitude_of_origin", 0.0],
    PARAMETER["central_meridian", 0.0],
    PARAMETER["scale_factor", 1.0],
    PARAMETER["false_easting", 0.0],
    PARAMETER["false_northing", 0.0],
    UNIT["m", 1.0],
    AXIS["Easting", EAST],
    AXIS["Northing", NORTH],
    AUTHORITY["EPSG","900913"]]
    </value>
  </property>
</bean>
```

You can add as many of these beans as needed. The keys transformation which are added this way are tested before the GeoTools library, so you can overwrite definitions if needed.

If you don't like the dependency on the gt-epsg-wkt library, then you could exclude this dependency in your maven pom and use a different dependency if needed.

---

## Part V. How-to

---

---

## Table of Contents

16. Writing your own commands .....	72
17. Create a plug-in .....	75
Using the plug-in archetype .....	75
Plug-in structure .....	75
Plug-in declaration and dependencies .....	75
18. Create a layer plug-in .....	76
Writing your own layer .....	76
19. Create a security plug-in .....	77
Writing your own security service .....	77

---

# Chapter 16. Writing your own commands

A Geomajas command usually consist of three classes, the actual command (which implements the Command interface), and two data transfer objects, one to pass the request parameters (extending CommandRequest, LayerIdCommandRequest or LayerIdsCommandRequest), and one which carries the response (extending CommandResponse).

It is important to assure your request object extends from LayerIdCommandRequest or LayerIdsRequest when one of the parameters is the layer id (or a list thereof). This can be used by the command dispatcher to assure the layer specific (transaction) interceptors are called.

To create a new command we recommend you use a similar package structure as we used in the geomajas-extension-command module. That is to create a "command" package with under that a "dto" package which contains all the request and response objects, and to put the actual commands in sub packages based on some kind of grouping. This helps to automatically determine a sensible command name.

The basic command implementation looks like this:

## Example 16.1. Example command template

```
package com.my.program.command.mysuper;

import com.my.program.command.dto.MySuperDoItRequest;
import com.my.program.command.dto.MySuperDoItResponse;
import org.geomajas.command.Command;
import org.slf4j.LoggerFactory;
import org.slf4j.Logger;
import org.springframework.stereotype.Component;

/**
 * Simple example command.
 *
 * @author Joachim Van der Auwera
 */
@Component()
public class MySuperDoItCommand implements Command<MySuperDoItRequest, MySuperDoItResponse> {

    private final Logger log = LoggerFactory.getLogger(MySuperDoItCommand.class);

    public MySuperDoItResponse getEmptyCommandResponse() {
        return new MySuperDoItResponse();
    }

    public void execute(MySuperDoItRequest request, MySuperDoItResponse response) {
        log.debug("called");
        // ..... perform the actual command
    }
}
```

Note the presence of the "@Component" annotation which assures the command is registered. You could add the name under which the command needs to be registered in the annotation, but when that is omitted,



the default command name is derived from the fully qualified class name. In the example given here this results in command name "command.mysuper.DoIt".

The default way to determine the command name assumes there is a package named "command" in the fully qualified name of the implementing class. It will remove everything before that. It will then remove a "Command" suffix if any. Lastly, it will remove duplication between the intermediate package (between "command" and the class name) and the class name itself. Some examples:

**Table 16.1. Samples of command name resolution**

Fully qualified class name	Command name
my.app.command.DoIt	command.DoIt
my.app.command.super.DoIt	command.super.DoIt
my.app.command.super.DoItCommand	command.super.DoIt
my.app.command.super.SuperDoItCommand	command.super.DoIt
my.app.command.super.DoItSuperCommand	command.super.DoIt
my.app.command.super.CommandDoIt	command.super.CommandDoIt
my.app.command.super.CommandSuperDoIt	command.super.CommandSuperDoIt
my.app.command.super.CommandDoItSuper	command.super.CommandDoIt

You have to include a line in your Spring configuration to scan class files for annotation to make the components available. For the case above, this could be done by including the following XML fragment in one of your Spring configuration files.

### Example 16.2. Scan to assure command is available

```
<context:component-scan base-package="com.my.program" name-generator="org.geomajas
```

The command will be executed using a singleton. The use of object variables is not recommended. Any object variables will be shared amongst all command invocation, which can be coming from multiple threads at the same time.

Note that it is not mandatory to create your own request and response object classes. If you don't require any parameters you can use `EmptyCommandRequest` as request class. If you only require a layer id, then use `LayerIdCommandRequest`. If you only return a success code, you could use the `SuccessCommandResponse` class.

You have to take care that all objects which are referenced by your request and response objects are actually serializable for the faces in which the commands need to be used. For the dojo face this may require the use of the "@Json" annotation to exclude fields. For GWT you have to assure the no-arguments constructor exists and that the class can be compiled by GWT (no Hibernate enhanced classes, no use of `super.clone()`,...).

When the commands are included in a separate module, you should assure the sources are available as these are needed for GWT compilation. This can easily be done using the Maven source plugin.

**Example 16.3. Maven source plugin**

```
<plugin>
  <groupId>org.apache.maven.plugins</groupId>
  <artifactId>maven-source-plugin</artifactId>
  <version>2.1.2</version>
  <executions>
    <execution>
      <goals>
        <goal>jar</goal>
      </goals>
      <configuration>
        <includePom>true</includePom>
      </configuration>
    </execution>
  </executions>
</plugin>
```

Actually including the sources can then be done using a dependency like the following (this includes the staticsecurity module, both the actual code and the sources). You could set "provided" scope on the source dependency to exclude it from the war file. However, this may prevent use of GWT development mode.

**Example 16.4. staticsecurity source plugin - including source**

```
<dependency>
  <groupId>org.geomajas.plugin</groupId>
  <artifactId>geomajas-plugin-staticsecurity</artifactId>
  <version>${geomajas-plugin-staticsecurity-version}</version>
</dependency>
<dependency>
  <groupId>org.geomajas.plugin</groupId>
  <artifactId>geomajas-plugin-staticsecurity</artifactId>
  <version>${geomajas-plugin-staticsecurity-version}</version>
  <classifier>sources</classifier>
</dependency>
<dependency>
  <groupId>org.geomajas.plugin</groupId>
  <artifactId>geomajas-plugin-staticsecurity-gwt</artifactId>
  <version>${geomajas-plugin-staticsecurity-version}</version>
</dependency>
<dependency>
  <groupId>org.geomajas.plugin</groupId>
  <artifactId>geomajas-plugin-staticsecurity-gwt</artifactId>
  <version>${geomajas-plugin-staticsecurity-version}</version>
  <classifier>sources</classifier>
</dependency>
```

---

# Chapter 17. Create a plug-in

The general procedure for creating a new plug-in is described here. Additional information for specific types of plug-ins is described in subsequent chapters.

## Using the plug-in archetype

TODO.....

## Plug-in structure

TODO.....

## Plug-in declaration and dependencies

TODO.....

---

# Chapter 18. Create a layer plug-in

Layers allow access to data which needs to be displayed in a map.

For the existing layers, the details about configuring you map to include that layer are included in the configuration section above.

## Writing your own layer

TODO.....

---

# **Chapter 19. Create a security plug-in**

## **Writing your own security service**

TODO.....

---

## **Part VI. Appendices**

---

---

## Table of Contents

A. Migrating between Geomajas versions .....	80
Migrating between Geomajas 1.6.0 and Geomajas (back-end core) 1.7.1 .....	80
Migrating from Geomajas 1.5.4 to Geomajas 1.6.0 .....	80
Migrating from Geomajas 1.5.3 to Geomajas 1.5.4 .....	81
Migrating from Geomajas 1.5.2 to Geomajas 1.5.3 .....	82
General API changes .....	83
Configuration changes .....	83
Migrating from Geomajas 1.5.1 to Geomajas 1.5.2 .....	86
Migrating from Geomajas 1.5.0 to Geomajas 1.5.1 .....	86
Migrating from Geomajas 1.4.x to 1.5.0 .....	86

---

# Appendix A. Migrating between Geomajas versions

## Migrating between Geomajas 1.6.0 and Geomajas (back-end core) 1.7.1

- `ApplicationContextUtils` has been renamed to `ApplicationContextUtil` and is now included in the api (this was done to adhere to the coding style).
- When building the dojo face and the dojo-example application, the maven "-PnoShrink" has been replaced by "-DskipShrink".
- The use of the dispatcher servlet was introduced in 1.7.1. It is strongly recommended that you include it in your web.xml file to assure all plug-ins which expect this can function.

```
<servlet>
  <servlet-name>dispatcher</servlet-name>
  <servlet-class>org.springframework.web.servlet.DispatcherServlet</servlet-cla
  <init-param>
    <param-name>contextConfigLocation</param-name>
    <param-value>classpath*:META-INF/geomajasWebContext.xml</param-value>
    <description>Spring Web-MVC specific (additional) context files.</descrip
  </init-param>
  <load-on-startup>3</load-on-startup>
</servlet>

<servlet-mapping>
  <servlet-name>dispatcher</servlet-name>
  <url-pattern>/d/*</url-pattern>
</servlet-mapping>
```

- the "springsecurity" module has been renamed "staticsecurity" to more correctly address the nature of the plug-in and to avoid possible confusion with Spring's security stuff. Additionally the old module has been split in two, one part being the back-end/configuration module, and another the gwt module.
- Many of the layers contain a bug in the 1.6.0 version assuming that injected services are fully initialised (and thus usable) while building the application context. Because of changes in the implementation of some services, these bugs become visible when using the 1.7 back-end. You have to update your layers as well to 1.7+ to avoid these problems.

## Migrating from Geomajas 1.5.4 to Geomajas 1.6.0

- The gwt-client module no longer automatically adds the "nl" locale to the application. This should now be done by the application. You can do this by adding the line

```
<extend-property name="locale" values="nl"/>
```

to your gwt.xml file.



- In the GWT face, you should now use `MapContext` instead of directly accessing `GraphicsContext`.
- `RasterLayer.paint()` now throws `GeomajasException` instead of `RenderException`. The `RenderException` class has been moved to `api-experimental`.
- `LocaleSelect` now needs a parameter in the constructor. This parameter is the name of the default language.
- The `OpenStreetMap` layer changes changed `groupId` from `"geomajas-layer-opentreetmaps"` to `"geomajas-layer-opentreetmap"`.
- `GeomajasSecurityException` has moved from `"org.geomajas.global"` to `"org.geomajas.security"`.
- `AllowAllSecurityService` has moved from `"org.geomajas.internal.security"` to `"org.geomajas.security.allowall"`.
- `VectorLayerService` and `RasterLayerService` have moved from `"org.geomajas.service"` to `"org.geomajas.layer"`.
- In `LabelStyleInfo` the style for the font is now of type `FontStyleInfo`.
- `LayerIdsCommandRequest` has been introduced and this is now extended by `SearchByLocationRequest` (no change) and `UserMaximumExtentRequest` (changing `includeLayers` to `layerIds`).

## Migrating from Geomajas 1.5.3 to Geomajas 1.5.4

- `SuccessCommandResponse` class contained typos. The methods `isSucces()` and `getSucces()` have been renamed to `isSuccess()` and `getSuccess()` respectively.
- Changes in pipeline and promotion to stable API.
- The method `getRasterLayer()` has been added in `ConfigurationService`.
- The `findMathTransform()` method in `GeoService` now throws `GeomajasException` instead of `FactoryException`.
- `InternalTile` changes (should not affect anybody as these are used internally in the back-end).
- Many `DtoConverterService` methods now throw `GeomajasException`.
- The method `getId()` has been added to `Layer`. All server layers should have a unique id. The id is automatically assigned based on the Spring bean name.
- Configuration changes: `maxTileLevel` has been removed as this was not used.
- Configuration changes: the server-side layers are no longer connected to the client-side layer configurations via the `layerInfo` objects. Instead, client-side layers refer directly to the server layer's id via a `serverLayerId` property. The references to the `layerinfo` objects are injected by a configuration postprocessor, so the `layerInfo` should no longer be set manually.

**Table A.1. Back end configuration changes**

Name	Property	Description
LayerInfo	id	Removed, use id property of Layer instead
SnappingRuleInfo	layerInfo	Replaced with serverLayerId
	serverLayerId	String ,should refer to id of Layer bean

**Table A.2. Client configuration changes**

Name	Property	Description
ClientLayerInfo	serverLayerId	String, should refer to id of Layer bean
	layerInfo	Should no longer be set manually, will be set by Spring

## Migrating from Geomajas 1.5.2 to Geomajas 1.5.3

- The `LayerModel` class has been integrated in `VectorLayer`. This modifies the configuration. Where before you would have written

```
<bean name="countriesModel" class="org.geomajas.layermodel.shapeinmem.ShapeInMemModel">
    <property name="url" value="classpath:shapes/africa/country.shp" />
</bean>
<bean name="countries" class="org.geomajas.internal.layer.layertree.DefaultVectorLayer">
    <property name="layerInfo" ref="countriesInfo" />
    <property name="layerModel" ref="countriesModel" />
</bean>
```

into

```
<bean name="countries" class="org.geomajas.layer.shapeinmem.ShapeInMemLayer">
    <property name="layerInfo" ref="countriesInfo" />
    <property name="url" value="classpath:shapes/africa/country.shp" />
</bean>
```

Note that this includes changing "layermodel" to "layer" in all module and package names.

- `FeaturePainter` interface and related stuff has been removed. These are obsolete with the introduction of the `VectorLayerService`.
- `GeotoolsLayer` has been renamed `GeoToolsLayer`.
- With the change in directory structure, the commands have moved from the `org.geomajas.extension.command` package to `org.geomajas.command`. The `LogCommand` has also been moved into the general sub-package.

- Security constraints are now applied in Geomajas. By default, nothing is authorized, so you always have to configure at least one security service. To go back to the old (allow-all) behaviour, include the following excerpt in your configuration file.

```
<bean name="security.securityInfo" class="org.geomajas.security.SecurityInfo">
    <property name="loopAllServices" value="false"/>
    <property name="securityServices">
        <list>
            <bean class="org.geomajas.security.allowall.AllowAllSecurityService"/>
        </list>
    </property>
</bean>
```

- Layers are now more sensitive to the attributes which are defined for the layer. Attributes which have not been defined in the feature info are not accessible this is the result of the refactoring where the `InternalFeature` store attributes as `Attribute` objects).

## General API changes

The `geomajas-API` has been split up in a formal (`geomajas-API`) and experimental API (`geomajas-api-experimental`). All interfaces/classes from the `cache` and `rendering` packages have been moved to `experimental`. This means that the rendering pipeline is at the moment not a part of the official API, but instead more of a preview of what's to come. Furthermore, some major changes have been made in many other packages:

- The `org.geomajas.rendering.tile` has been moved to `org.geomajas.layer.tile`
- Introduction of a `DtoConverterService` that is able to convert DTO objects from and to back-end internal representations.
- All the different feature definitions have been cut down. Only 2 versions remain at the moment: a DTO feature (`org.geomajas.layer.feature.Feature`) and a feature definition used internally in the backed (`org.geomajas.layer.feature.InternalFeature`).
- All the different tile definitions have been cut down. Only 3 remain. 2 DTO tiles: `org.geomajas.layer.tile.VectorTile` - used in vector layers and `org.geomajas.layer.tile.RasterTile` - used in raster layers. The third is the `org.geomajas.tile.InternalTile`. This tile is used internally on the back-end.
- `GeometricAttributeInfo` has been renamed to `GeometryAttributeInfo`.
- `ApplicationService` has been renamed to `ConfigurationService`.

## Configuration changes

The configuration API has been split up in a back-end part and a client (or faces) part. The following general rules have been kept in mind:

- Back-end configuration should be restricted to those properties that are functionally needed on the back-end. We essentially regard the back-end as a container of layers or, in WFS terms, feature types. Higher level concepts like map or application should be dealt with at the client (or faces) level.
- Client configuration should not impact the back-end state. In the near future, this will make it possible to reconfigure clients without restarting the server.

The configuration API has profoundly changed. Where possible, the back-end classes have retained their original (before the split) names, after pruning them to remove all client related information. The client classes have been mostly created from scratch and have been named `ClientXxxInfo.java` for consistency. They have been located in a separate package, called `org.geomajas.configuration.client`. The following table gives a top-down overview of the back-end configuration classes (new classes and properties have been marked in **bold**):

**Table A.3. Back end configuration changes**

Name	Property	Action or description
ApplicationInfo	*	removed
LayerInfo	label	moved to ClientLayerInfo
	visible	moved to ClientLayerInfo
	viewScaleMin, viewScaleMax	moved to ClientLayerInfo
VectorLayerInfo	labelAttribute	moved to LabelStyleInfo
	snappingRules	moved to ClientVectorLayerInfo
	styleDefinitions	replaced by namedStyleInfos
	creatable, updatable, deletable	moved to ClientVectorLayerInfo (automatically assigned)
	<b>namedStyleInfos</b>	list of NamedStyleInfo. Lists the predefined styles available for this layer. Multiple styles are possible so clients can choose a style
RasterLayerInfo	style	moved to ClientRasterLayerInfo
<b>NamedStyleInfo</b>	<b>featureStyles</b>	list of FeatureStyleInfo. Ordered list of style definitions with applicable filters. Together with the label style they define a single named layer style.
	<b>labelStyleInfo</b>	label attribute name and style
<b>FeatureStyleInfo</b>	*	replaces StyleInfo same properties except for index
	index	replaces id (automatically assigned)
<b>LabelStyleInfo</b>	*	replaces LabelAttribute, same properties
ValidatorInfo and XxxConstraintInfo	*	moved to package <code>org.geomajas.configuration.validation</code>

The most important changes are:

- The removal of client-side properties like visible, label, viewScaleMin, viewScaleMax, style and snapping rules. These are moved to the client configuration (see hereafter).
- The replacement of the single style definition list by a set of named styles. These are styles that are preconfigured in the back end.
- Inclusion of the label attribute name and style as part of the named style. This is more logical and in line with the SLD (Styled Layer Descriptor) specification.

The client or face classes are largely new and have been relocated to the `org.geomajas.configuration.client` package. The following table gives a top-down overview of the back-end configuration classes (new classes and properties have been marked in **bold**):

**Table A.4. Client configuration**

Name	Property	Action or description
<code>ClientApplicationInfo</code>	<code>name</code>	removed
<b><code>ClientMapInfo</code></b>	<code>maxBounds</code>	replaces <code>MapInfo</code> , optional maximum extent of the map, if present it will be used instead of the union of the layers' maximum extent
<b><code>ClientLayerInfo</code></b>	<code>label</code>	moved from <code>LayerInfo</code>
	<code>visible</code>	moved from <code>LayerInfo</code>
	<code>viewScaleMin</code> , <code>viewScaleMax</code>	moved from <code>LayerInfo</code>
	<code>layerInfo</code>	reference to back-end <code>LayerInfo</code>
	<code>maxExtent</code>	transformed extent from back-end
<b><code>ClientVectorLayerInfo</code></b>	<code>snappingRules</code>	moved from <code>VectorLayerInfo</code>
	<b><code>namedStyleInfo</code></b>	The style to apply on the layer. Should be a reference to one of the back-end layer's predefined styles (see <code>VectorLayerInfo</code> ).
	<code>creatable</code> , <code>updatable</code> , <code>deletable</code>	moved from <code>VectorLayerInfo</code>
	<b><code>featureInfo</code></b>	optional replacement of the back-end layer's <code>FeatureInfo</code> . If present, it is used instead.
<b><code>ClientRasterLayerInfo</code></b>	<code>style</code>	moved from <code>ClientRasterLayerInfo</code>
<b><code>ClientLayerTreeInfo</code></b>	*	rename of <code>LayerTreeInfo</code> , same properties
<b><code>ClientLayerTreeNodeInfo</code></b>	*	rename of <code>LayerTreeNodeInfo</code>
	<code>layers</code>	list of <code>ClientLayerInfo</code> objects, replaces previous list of layer ids
	<code>expanded</code>	changed from string to boolean
<b><code>ClientToolbarInfo</code></b>	*	rename of <code>ToolbarInfo</code>
<b><code>ClientToolInfo</code></b>	*	rename of <code>ToolInfo</code>

Apart from these changes in content, some general technical improvements have been made as well:

- The Spring bean name (or id) is used to set the id property of the class if there is one. This makes it unnecessary to define the id separately. The way this is done is by using a Spring `BeanPostProcessor`. (see `org.geomajas.internal.configuration.ConfigurationBeanPostProcessor`)
- Some calculations that were previously done in the `GetConfigurationCommand` are now done in the `ConfigurationBeanPostProcessor`.

- Cloning of the client configuration classes can be done with general deep cloning techniques like serialization, bypassing the need for custom cloneable implementations.

As usual, example configurations can be found in the application projects.

## Migrating from Geomajas 1.5.1 to Geomajas 1.5.2

- "layerRef" is renamed to "layerIds" in `LayerTreeNodeInfo`.

## Migrating from Geomajas 1.5.0 to Geomajas 1.5.1

- Configuration has changed from the proprietary format to using Spring configuration.
- There is now a `CommandDispatcher` service and official command names and defined request and response objects. Deprecated commands have been removed.

## Migrating from Geomajas 1.4.x to 1.5.0

- In your `application.xml`, you should change "OSMLayerFactory" to "OsmLayerFactory"
- In your `application.xml`, you should change "WMSLayerFactory" to "WmsLayerFactory"
- replace package "layermodels" with "layermodel"
- replace `"org.geomajas.core.application.DefaultLayerFactory"` with `"org.geomajas.internal.application.DefaultLayerFactory"`
- `mapWidget.addController()` and `mapWidget.removeController()` have been removed. They are replaced by `mapWidget.setController()`. You could only add one controller anyway.